

**Main page:** [Cisco Unified MeetingPlace, Release 7.0](#)

**Up one level:** [Reference Information](#)

**Note:** In the following table, TUI stands for Telephone User Interface.

**Table: Export Data Specifications-Meeting Participant Information**

Field Name	Description	Size and Type of Value
PartId	See <a href="#">PartID</a> .	0 to 17 ASCII text characters
ConfNum	See <a href="#">ConfNum</a> .	1 to 9 numeric characters
uid	<a href="#">User ID</a> of the meeting participant.	1 to 30 alphanumeric characters
MeetingId	Meeting ID.	Numeric characters
StartTimeOfConf	Date and time when the meeting started.	MM/DD/YYYY hh:mm
nVSecInConf	Amount of time, in seconds, that the participant spent in the voice portion of the meeting.	An unsigned integer
nWFSecInConf	<i>Not supported.</i>	-
nSecsOutboundCalls	Amount of time, in seconds, that the participant spent in a call that was dialed out by the system.	An unsigned integer
VNameHeader	Whether the name of the participant was recorded.	Recorded/Not_Recorded
nOutboundCalls	Number of dial-out calls initiated by this participant	An unsigned integer
nRetries	Number of dial-out retries initiated by this participant	An unsigned integer
TNameHeader	<p><a href="#">First name</a> and <a href="#">Last name</a> of the meeting participant.</p> <p>For unprofiled participants, this displays one of the following:</p> <ul style="list-style-type: none"> <li>Name the guest user enters to join the meeting from the end-user web interface.</li> <li>"Guest User" followed by the phone number or extension from which the user dials in.</li> </ul>	0 to 64 alphanumeric characters
SpeakingAbility	<p>Speaking ability of the participant upon leaving the meeting.</p> <p>Upon entering the meeting, the participant has one of the following speaking abilities:</p> <ul style="list-style-type: none"> <li>LISTENER-Audience/Listener</li> <li>SPEAKER-Audience/Speaker or Presenter/Speaker</li> <li>SPEAKERPLUS-Moderator/Speaker</li> </ul> <p>In collaborative meetings, all participants are speakers.</p>	<ul style="list-style-type: none"> <li>LISTENER</li> <li>SPEAKER</li> <li>SPEAKERPLUS</li> <li>MUTED_SPEAKER</li> <li>MUTED SPEAKERPLUS</li> </ul>

	<p>The moderator may change the speaking abilities of participants via lecture-style meeting controls, for example:</p> <ul style="list-style-type: none"> <li>• Opening the floor converts all listeners to speakers.</li> <li>• Closing the floor converts all speakers to listeners.</li> <li>• Moderators are always speakers.</li> </ul> <p>Note, however, that the mute state is controlled by the individual participant, not the moderator. Each speaker chooses whether or not to be muted. Listeners cannot mute or unmute themselves.</p>	
nVUIODsMade	Number of dial-out calls that this participant initiated from the TUI.	An unsigned integer
nTimesQAsked	Number of times a question was asked by the participant.	An unsigned integer
nTimesFGiven	Number of times the floor was given to the participant.	Integer
UpdateTime	When this record was most recently updated.	MM/DD/YYYY hh:mm
nDCSecInConf	Amount of time, in seconds, that the user spent in the web meeting room.	An unsigned integer
nSecInMTGNotes	Amount of time, in seconds, that the user spent listening to recordings and other notes for this meeting.	An unsigned integer

#### Related Topics

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace](#)