

The following information describes how to install or upgrade Cisco Unified MeetingPlace for Jabber on a Jabber server so that users can initiate Cisco Unified MeetingPlace meetings from a Jabber Messenger client.

## Contents

- 1 Pre-Installation Tasks
  - ◆ 1.1 Enabling the Jabber Integration Option Key
    - ◇ 1.1.1 To Enable the Jabber Integration Option Key
- 2 Setting the JABBER\_HOME Environment Variable
  - ◆ 2.1 Procedure
- 3 About the Cisco Unified MeetingPlace for Jabber Installer
- 4 Installing Cisco Unified MeetingPlace for Jabber by Using the Command-Line Installer
  - ◆ 4.1 To Install Cisco Unified MeetingPlace for Jabber by Using the Command-Line Installer
- 5 Installing Cisco Unified MeetingPlace for Jabber by Using the X-Windows GUI Installer
  - ◆ 5.1 To Install Cisco Unified MeetingPlace for Jabber by Using the X-Windows GUI Installer
- 6 Upgrading or Reinstalling Cisco Unified MeetingPlace for Jabber
  - ◆ 6.1 To Stop the Cisco External Command Interface
- 7 Uninstalling Cisco Unified MeetingPlace for Jabber
  - ◆ 7.1 To Stop and Remove the Cisco External Command Interface
  - ◆ 7.2 To Delete the Cisco Unified MeetingPlace for Jabber Files
  - ◆ 7.3 To Remove the Component Reference from the Jabber.Jig File

## Pre-Installation Tasks

Do the tasks in this section before installing Cisco Unified MeetingPlace for Jabber:

1. Confirm that the Jabber server meets the requirements listed in the "Integration Requirements: Jabber Server" section of the System Requirements.
2. Add a feature license option key for Cisco Unified MeetingPlace for Jabber to the Cisco Unified MeetingPlace Audio Server. See the Enabling the Jabber Integration Option Key.
3. Confirm that you have root access to the Jabber server. You must run the installer from the root account on the Jabber server.
4. Set the JABBER\_HOME environment variable for the root account on the Jabber server to point to the directory in which Jabber is installed. See the Setting the JABBER\_HOME Environment Variable.

## Enabling the Jabber Integration Option Key

An option key is an alphanumeric string similar to a serial number that needs to be entered in the Cisco Unified MeetingPlace database to activate a system option. You use the MeetingTime client to enter option keys. (For more information, see [About Loading License Keys](#).)

### To Enable the Jabber Integration Option Key

1. On your license for Cisco Unified MeetingPlace Audio Server, locate the Jabber Integration option key.
2. Start MeetingTime and log in to the Cisco Unified MeetingPlace Audio Server.
3. Click **Administration > Configure**.
4. Click **System Options**, then click **Query**.
5. Use the right arrow button to locate the Jabber Integration option.
6. Click **Option Key**, then enter the option key number that you made note of in [Step 1](#) and click **OK**.
7. Click **Save Changes** and restart the Cisco Unified MeetingPlace Audio Server for the option keys to take effect.

## Setting the JABBER\_HOME Environment Variable

Before you install Jabber with Cisco Unified MeetingPlace, set the JABBER\_HOME environment variable for the root account on the Jabber XCP server to point to the directory in which Jabber is installed.

### Procedure

1. Log in to the Jabber XCP server as root.
2. Enter **bash** at the command line.
3. Enter **JABBER\_HOME=<Path to the directory in which Jabber is installed>**, where *<Path to the directory in which Jabber is installed>* is the path to the directory in which Jabber is installed. For example, enter **JABBER\_HOME=/opt/jabber**.
4. Enter **export JABBER\_HOME**.
5. Enter **echo \$JABBER\_HOME** to confirm the setting.

The system displays the path to the directory in which Jabber is installed.

## About the Cisco Unified MeetingPlace for Jabber Installer

You install Cisco Unified MeetingPlace for Jabber on a Jabber server by using either a command-line interface, such as a console, or by using the graphical user interface (GUI) in X-Windows. The same installer is used in both cases; the interface you use to launch the installer determines whether you receive the command-line interface or the GUI interface.

You must run the installer from the root account on the Jabber server. Your deployment must include a Cisco Unified MeetingPlace Web Conferencing server running Release 6.1.

Before installing Cisco Unified MeetingPlace for Jabber, confirm that the Jabber server meets the requirements listed in the "Integration Requirements: Jabber Server" section of the [System Requirements](#).

## Installing Cisco Unified MeetingPlace for Jabber by Using the Command-Line Installer

### To Install Cisco Unified MeetingPlace for Jabber by Using the Command-Line Installer

1. Log in to the Jabber server as root.
2. The Cisco Unified MeetingPlace Jabber Integration CD contains a binary file called `install_jabber_6_x_x_x.bin`, where `6_x_x_x` is the version number. Insert the CD into the CD or DVD-ROM drive on the Jabber server, or copy the file to the server from another location.
3. At the command line, type the path to the binary install file, and press **Enter**.
4. Confirm that you want to install Cisco Unified MeetingPlace for Jabber by pressing **Enter**.
5. Choose the path where Cisco Unified MeetingPlace for Jabber will be installed. The path must match the path where the Jabber application is installed. Press **Enter** to accept the default path, or type a path and press **Enter**.
6. Review the installation information. To proceed with the installation, press **Enter**.

## Installing Cisco Unified MeetingPlace for Jabber by Using the X-Windows GUI Installer

### To Install Cisco Unified MeetingPlace for Jabber by Using the X-Windows GUI Installer

1. Log in to the Jabber server as root.
2. The Cisco Unified MeetingPlace Jabber Integration CD contains a binary file called `install_jabber_6_x_x_x.bin`, where `6_x_x_x` is the version number. Insert the CD into the CD or DVD-ROM drive on the Jabber server, or copy the file to the server from another location.
3. In a command window, type the path to the binary install file, and press **Enter**.
4. Confirm that you want to install Cisco Unified MeetingPlace for Jabber by clicking **Next**.
5. Choose the path where Cisco Unified MeetingPlace for Jabber will be installed. The path must match the path where the Jabber application is installed. Click **Next** to accept the default path, or type a path and click **Next**.
6. Review the installation information. To proceed with the installation, click **Next**. To cancel the installation, click **Cancel**.

## Upgrading or Reinstalling Cisco Unified MeetingPlace for Jabber

Do the tasks in this section to upgrade or to reinstall Cisco Unified MeetingPlace for Jabber. Do them only if you have already completed configuration of Cisco Unified MeetingPlace for Jabber. (See [Configuring Cisco Unified MeetingPlace for Jabber](#))

1. Review [Upgrading to Cisco Unified MeetingPlace Release 6.1](#).

2. Stop the Cisco External Command Interface component. See the [To Stop the Cisco External Command Interface](#).
3. If you are upgrading from Cisco Unified MeetingPlace for Jabber Release 5.4, add a feature license key for Cisco Unified MeetingPlace for Jabber to the Cisco Unified MeetingPlace Audio Server. See the [To Enable the Jabber Integration Option Key](#).
4. Run the installer by using either the [To Install Cisco Unified MeetingPlace for Jabber by Using the Command-Line Installer](#) or the [To Install Cisco Unified MeetingPlace for Jabber by Using the X-Windows GUI Installer](#).

#### To Stop the Cisco External Command Interface

1. Log on to the Jabber XCP Controller web interface. Refer to the Jabber documentation for information on how to access the interface.
2. From the XCP Controller home page, in the Components section, locate the Cisco External Command Interface component.
3. In the Actions column, click **Stop**.

## Uninstalling Cisco Unified MeetingPlace for Jabber

This section contains three procedures. Do them in the order listed to uninstall Cisco Unified MeetingPlace for Jabber.

Do the procedures only if you have already completed configuration of Cisco Unified MeetingPlace for Jabber. (See [Configuring Cisco Unified MeetingPlace for Jabber](#))

#### To Stop and Remove the Cisco External Command Interface

1. Log on to the Jabber XCP Controller web interface. Refer to the Jabber documentation for information on how to access the interface.
2. From the XCP Controller home page, in the Components section, locate the Cisco External Command Interface component.
3. In the Actions column, click **Stop**.
4. In the Remove column, click **Remove**.

#### To Delete the Cisco Unified MeetingPlace for Jabber Files

1. From a command window on the Jabber server, locate the JAR file directory-the `./lib/cisco` subdirectory of the directory that contains the installer source files (for example, `/opt/jabber/lib/cisco`).
2. Enter `rm -rf <Path to JAR File Directory from Step 1>` and press **Enter**.
3. Locate the Cisco JIG configuration directory-the `./schemas/jig/config/cisco` subdirectory of the directory that contains the installer source files (for example, `/opt/jabber/schemas/jig/config/cisco`).
4. Enter `rm -rf <Path to Cisco JIG Configuration File Directory from Step 3>` and press **Enter**.
5. Locate the Cisco XSD configuration directory-the `./schemas/xsd/config/cisco` subdirectory of the directory that contains the installer source files (for example, `/opt/jabber/schemas/xsd/config/cisco`).
6. Enter `rm -rf <Path to Cisco XSD Configuration File Directory from Step 5>` and press **Enter**.

**To Remove the Component Reference from the Jabber.Jig File**

1. From a command window on the Jabber server, locate the jabber.jig file (for example, /opt/jabber/schemas/jig/config/jabber/jabber.jig).
2. Open the **jabber.jig** file in a text editor.
3. Find and remove the following line of text: **<xi:include xi:href="{JABBER\_HOME}/schemas/jig/config/cisco/cisco.jig" level="base"/>**
4. Save and close the **jabber.jig** file.