

**Main page:** [Cisco Unified MeetingPlace, Release 8.0](#)

**Up one level:** [Reference Information](#)

Use these specifications when importing data to Cisco Unified MeetingPlace or exporting data from Cisco Unified MeetingPlace to a spreadsheet or database program:

- [User Groups-Raw Data Export and Import Specifications](#)
- [User Profiles-Raw Data Export and Import Specifications](#)
- [Video Terminal Profiles-Raw Data Export and Import Specifications](#)
- [Meetings-Raw Data Export and Import Specifications](#)
- [Outgoing Calls Information-Raw Data Export Specifications](#)
- [Meeting Participant Information-Raw Data Export Specifications](#)
- [Meeting Participant Join Leave Information-Raw Data Export Specifications](#)
- [Scheduling Failures Information-Raw Data Export Specifications](#)
- [Scheduling Statistics Information-Raw Data Export Specifications](#)
- [Scheduling Activity By User Information-Raw Data Export Specifications](#)
- [Continuous Meetings Information-Raw Data Export Specifications](#)

## Contents

- [1 User Groups-Raw Data Export and Import Specifications](#)
  - ◆ [1.1 Table: Import and Export Data Specifications for User Groups](#)
  - ◆ [1.2 Related Topics](#)
- [2 User Profiles-Raw Data Export and Import Specifications](#)
  - ◆ [2.1 Table: Import and Export Data Specifications for User Profiles](#)
  - ◆ [2.2 Related Topics](#)
- [3 Video Terminal Profiles-Raw Data Export and Import Specifications](#)
  - ◆ [3.1 Table: Import and Export Data Specifications for Video Terminal Profiles](#)
  - ◆ [3.2 Related Topics](#)
- [4 Meetings-Raw Data Export and Import Specifications](#)
  - ◆ [4.1 Table: Import and Export Data Specifications for Meetings](#)
  - ◆ [4.2 Related Topics](#)
- [5 Outgoing Calls Information-Raw Data Export Specifications](#)
  - ◆ [5.1 Table: Export Data Specifications-Outgoing Calls Information](#)
  - ◆ [5.2 Related Topics](#)
- [6 Meeting Participant Information-Raw Data Export Specifications](#)
  - ◆ [6.1 Table: Export Data Specifications-Meeting Participant Information](#)
  - ◆ [6.2 Related Topics](#)
- [7 Meeting Participant Join Leave Information-Raw Data Export Specifications](#)
  - ◆ [7.1 Table: Export Data Specifications-Meeting Participant Join Leave Information](#)
  - ◆ [7.2 Related Topics](#)
- [8 Scheduling Failures Information-Raw Data Export Specifications](#)

- ◆ [8.1 Table: Export Data Specifications-Scheduling Failures Information](#)
- ◆ [8.2 Table: Failure Code Reference: Scheduling Failures Information](#)
- ◆ [8.3 Related Topics](#)
- [9 Scheduling Statistics Information-Raw Data Export Specifications](#)
  - ◆ [9.1 Table: Export Data Specifications-Scheduling Statistics Information](#)
  - ◆ [9.2 Related Topics](#)
- [10 Scheduling Activity By User Information-Raw Data Export Specifications](#)
  - ◆ [10.1 Table: Export Data Specifications-Scheduling Activity By User Information](#)
  - ◆ [10.2 Related Topics](#)
- [11 Continuous Meetings Information-Raw Data Export Specifications](#)
  - ◆ [11.1 Table: Export Data Specifications-Continuous Meetings Information](#)
  - ◆ [11.2 Related Topics](#)

## User Groups-Raw Data Export and Import Specifications

**Note:** The first line in the export file specifies the Cisco Unified MeetingPlace version. If you want to import this file or use this file as a template for importing data, you must *not* modify this line.

**Table: Import and Export Data Specifications for User Groups**

Field Name	Description	Size and Type of Value
ContactID	See <a href="#">User ID of delegate</a> .	1 to 30 alphanumeric characters
tzcode	See <a href="#">Time zone</a> .  Import requirements: <ul style="list-style-type: none"> <li>• The integer value in the import file must match a value defined by Cisco Unified MeetingPlace. Make sure you use a previously exported value.</li> <li>• If the import file contains the <a href="#">tzcode</a> header field, all user groups in the import file must have a valid entry for the field. For any invalid or blank <a href="#">tzcode</a> values, the associated user group is not imported, and an error is logged.</li> </ul>	0 to 17 ASCII text characters
BillCode	See <a href="#">Billing code</a> .	0 to 17 alphanumeric characters
grpnum	See <a href="#">Number</a> .	1 to 17 alphanumeric characters

	Import requirement: This field is required in the import file whether you are adding or deleting user groups by import.	
Name	See <u>Name</u> .  Import requirement: This field is required in the import file whether you are adding or deleting user groups by import.	1 to 17 alphanumeric characters
IsActive	See <u>User status</u> .	Yes/No
IsAdvancedPrompts	<i>Not supported</i> .  Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-
CanOutdial	See <u>Can dial out (does not apply to Cisco WebEx meetings)</u> .	Yes/No
NamedDisconnect	See <u>Departure announcement</u> .	Beep only/Beep + name/Silent
NamedIntroduction	See <u>Entry announcement</u> .	Beep only/Beep + name/Silent
PasswordRequired	See <u>Meeting password required</u> .	Yes/No
ScreenedIntroduction	See <u>Screened entry</u> .	Yes/No
RecordMeetings	See <u>Can record meetings</u> .	Yes/No
QuickMtgEntryAllowed	<i>Not supported</i> .  Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
PasswordRequiredOnOD	<i>Not supported</i> .	-
MeetingRestriction	See <u>Who can attend</u> .	Anyone/Users/Invited Users/None
CanRecordMeetings	See <u>Can record meetings</u> .  Import restriction: If you set this to No, the following fields are also set to No during the import process:  <ul style="list-style-type: none"> <li>• <u>RecordMeetings</u> ()</li> <li>• <u>autostrtrcrd</u> (Auto-start recording)</li> </ul>	Yes/No
MtgNoteRestriction	See <u>Who can access</u> .	Anyone/Users/Invited Users/None
ODXLatTableNum	<i>Not supported</i> .  Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-

Table: Import and Export Data Specifications for User Groups

MaxImmedMtgsPerDay	See <u>Scheduling restriction (meetings to start within 6 hours of scheduling)</u> .	<ul style="list-style-type: none"> <li>• Numeric-range is 0 to 50</li> <li>• 10000-Unrestricted*</li> <li>• 10001-Cannot schedule</li> </ul>
MaximumMeetingLength	See <u>Maximum meeting length (minutes)</u> .  Import restriction: This cannot exceed the value of the <u>Maximum meeting length (minutes)</u> field on the <u>Meeting Configuration Page</u> .	Numeric-range is 0 to 1440
MaxVUIODsPerMtg	See <u>Maximum TUI dial-out attempts per meeting</u> .	<ul style="list-style-type: none"> <li>• Numeric-range is 0 to 500</li> <li>• 10000 (unrestricted)</li> </ul>
nondidpgrnum	See <u>Phone number for non-direct-dial pagers</u> .	<p>0 to 32 characters of the following types:</p> <ul style="list-style-type: none"> <li>• numeric</li> <li>• ()-</li> <li>• space ( )</li> </ul>
faxnum	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new group, leave this field blank.	-
maxattsprmtg	<i>Not supported.</i>	-
rcvnotifs	See <u>Can receive notifications</u> .	Yes/No
site	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-
preferredunit	See <u>Schedule home server</u> .  Import restriction: Cisco Unified MeetingPlace Release 8.0 supports a smaller range of values than earlier releases. If you import user groups that were originally configured for an earlier release system, make sure that you adjust this value accordingly.	Numeric-range is 0 to 999
atndprf	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>UserCallsIn</b> .	-

Table: Import and Export Data Specifications for User Groups

prmrynotifprf	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>EMail</b>.</p>	-
altnotifprf	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Unknown_NotPref_Type</b>.</p>	-
pgrtype	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>DIDPager</b>.</p>	-
emailtype	<p>See <u>Email type and format</u>, which combines the <u>emailtype</u> and <u>EmailFormat</u> fields.</p> <p><b>Note:</b> The <u>emailtype</u> value determines which options are supported in the <u>EmailFormat</u> field.</p>	SMTP/Exchange/LotusNotes
faxlatablenum	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b>.</p>	-
sndnotifs	See <u>Can send notifications</u> .	Yes/No
autodistatts	<i>Not supported.</i>	-
dfltnotifprio	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Normal</b>.</p>	-
sndnotifonmtgch	See <u>Send if meeting changes</u> .	Yes/No
sndinvlstwnotif	See <u>Include invitee list when scheduled from web</u> .	Yes/No
sndmtgpwdwnotif	See <u>Include meeting password</u> .	Yes/No
rcvattswnotif	<i>Not supported.</i>	-
playattlstfifo	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Yes</b>.</p>	-
schedprefunitonly	<i>Not supported.</i>	-

Table: Import and Export Data Specifications for User Groups

	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	
autostrtrcrd	See <u>Auto-start recording</u> .	Yes/No
disablerollcall	See <u>Disable roll call</u> .	Yes/No
schedhomesiteonly	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Yes</b> .	-
concurrentquestions	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-
announceqarr	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Beep + name</b> .	-
announceqdep	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Beep + name</b> .	-
fqnadisable	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
ftellpartpos	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
fadvanceinfo	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
fautoproenabled	<i>Not supported.</i>	-

Table: Import and Export Data Specifications for User Groups

	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	
fstartpeopleinwr	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>admitaslisteners</b> .	-
publiculallowed	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>10</b> .	-
groupulallowed	<i>Not supported.</i>	-
privateulallowed	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-
meetingcategory	See <u>Default meeting category</u> .	Up to 20 alphanumeric characters
numdataparts	<i>Not supported.</i>	-
chatclienttype	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-
fallowdataconf	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
fchatsession	<i>Not supported.</i>	-
fismtgseminartype	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
fallowguestview	See <u>Show meetings in public listing</u> .	Yes/No
qnanotify	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
fCanInviteRemoteServers	<i>Not supported.</i>	-

Table: Import and Export Data Specifications for User Groups

canallowguestoutdial	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	
allowguestoutdial		
VLanguage	See <u>Language</u> .	0 to 128 alphanumeric characters
fEndMtgWarn	<i>Not supported.</i>	-
fMtgExtendPrompts	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
SSI_SystemID	<i>Not supported.</i>	-
SSI_RollMapID	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-
SSI_SiteID		
CanChangeMtgID	See <u>Can change meeting ID via phone</u> .	Yes/No
RsvnlessCnfg	See <u>Use reservationless</u> .	<ul style="list-style-type: none"> <li>• 0-Yes</li> <li>• 1-No</li> </ul>
AllowVideoSched	<i>Not supported.</i>	-
	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
AllowInternetAccess	See <u>Allow Internet access</u> .	Yes/No
VideoEndPtBandwidth	<i>Not supported.</i>	-
	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>384K</b> .	-
EmailFormat	<p>See <u>Email type and format</u>, which combines the <u>emailtype</u> and <u>EmailFormat</u> fields.</p> <p>Only the following combinations of <u>emailtype</u> and <u>EmailFormat</u> fields are supported:</p> <ul style="list-style-type: none"> <li>• SMTP/html</li> <li>• SMTP/txt</li> <li>• LotusNotes/txt</li> <li>• Exchange/html</li> <li>• Exchange/txt</li> </ul>	txt/html/RTF
ReserveVoiceLicenses	<i>Not supported.</i>	-

Table: Import and Export Data Specifications for User Groups



	Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Yes</b> .	
CanReserveVideoPorts	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>No</b> .	-
PreferVideo	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>Yes</b> .	-
FRsvnAllowGuestView	See <a href="#">Show reservationless meetings in public listing</a> .	Yes/No
attendMode	See <a href="#">Auto attend mode</a> .	<ul style="list-style-type: none"> <li>• 0-None</li> <li>• 1-Automatically join meeting*</li> <li>2-Automatically sign in</li> </ul>
attendPasswdRequired	See <a href="#">Auto attend requires profile PIN</a> .	Yes/No
FRsvnlessAllowInternetAcc	See <a href="#">Reservationless allow Internet access</a> .	Yes/No
videoTypes	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>0</b> .	-
mtgEntryMode	See <a href="#">Meeting entry mode</a> .	<ul style="list-style-type: none"> <li>• 0-Echo meeting</li> <li>• 1-Skip ID repeat*</li> <li>3-Skip ID repeat and skip names</li> </ul>
dataConfClientType	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>1</b> .	-

#### Related Topics

- [Exporting User Groups](#) in the [Running Reports and Exporting Data from Cisco Unified MeetingPlace](#) module
- [Adding or Editing User Groups by Import](#) in the [Importing Data into Cisco Unified MeetingPlace](#) module
- [Deleting User Groups by Import](#) in the [Importing Data into Cisco Unified MeetingPlace](#) module

## User Profiles-Raw Data Export and Import Specifications

**Note:** The first line in the export file specifies the Cisco Unified MeetingPlace version. If you want to import this file or use this file as a template for importing data, you must *not* modify this line.

**Table: Import and Export Data Specifications for User Profiles**

Field Name	Description	Size and Type of Value
fnm	See <u>First name</u> .	0 to 32 alphanumeric characters
lnm	See <u>Last name</u> .	0 to 32 alphanumeric characters
uid	See <u>User ID</u> .  Import requirement: This field is required whether you are adding or deleting user profiles by import.	1 to 30 alphanumeric characters
prfnum	See <u>Profile number</u> .  Import requirement: This field is required whether you are adding or deleting user profiles by import.	1 to 32 numeric characters
phnum	See <u>Main phone number</u> .	0 to 32 alphanumeric characters
ctctuid	See <u>User ID of delegate</u> .  Import requirement: If not set to gd (1), the value must match one of the following: <ul style="list-style-type: none"> <li>• <u>User ID</u> in the Cisco Unified MeetingPlace database</li> <li>• <u>uid</u> in the import file</li> </ul> Restriction: The specified user must be of type <u>Delegate</u> .	1 to 30 alphanumeric characters
grpname	See <u>Group name</u> .  Import requirement: If the import file contains the <u>grpname</u> header field, all user profiles in the import file must have a valid entry for this field. For details, see <u>Adding or Editing User Profiles by Import</u> in the <u>Importing Data into</u>	1 to 17 alphanumeric characters

	Cisco Unified MeetingPlace module.	
grpnum	See <u>Number</u> .  Import requirement: If the import file contains the <u>grpnum</u> header field, all user profiles in the import file must have a valid entry for this field. For details, see <u>Adding or Editing User Profiles by Import</u> in the <u>Importing Data into Cisco Unified MeetingPlace</u> module.	0 to 17 numeric characters
tzcode	See <u>Time zone</u> .  Import requirements: <ul style="list-style-type: none"> <li>• The integer value in the import file must match a value defined by Cisco Unified MeetingPlace. Make sure you use a previously exported value.</li> <li>• If the import file contains the <u>tzcode</u> header field, all user profiles in the import file must have a valid entry for the field. For any invalid or blank <u>tzcode</u> values, the associated user profile is not imported, and an error is logged.</li> </ul>	0 to 17 ASCII text characters
abbprmts	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
anndpart	See <u>Departure announcement</u> .	Beep+ name/Beep only/Silent/gd
annentry	See <u>Entry announcement</u> .	Beep+ name/Beep only/Silent/gd
pwdreq	See <u>Meeting password required</u> .	Yes/No/gd
screntry	See <u>Screened entry</u> .	Yes/No/gd
bcode	See <u>Billing code</u> .	0 to 17 alphanumeric characters
uactive	See <u>User status</u> .	Yes/No/gd/Locked
utype	See <u>Type of user</u> .	EndUser/Delegate/Attendant/SysMgr
ndial	See <u>Can dial out (does not apply to Cisco WebEx meetings)</u> .	Yes/No/gd
shrtmnus	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new	-

Table: Import and Export Data Specifications for User Profiles

	profile, enter <b>gd</b> .	
pwdonoutdial	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
whocanattnd	See <u>Who can attend</u> .	Anyone/Users/ Invited Users/None
whocanlstn	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
canrecord	See <u>Can record meetings</u> .	Yes/No/gd
recordmtgs	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
WFPASSWORDLastChanged	<i>Display only.</i> When the <u>User password</u> was last changed.	MM/DD/YYYY hh:mm
VUPASSWORDLastChanged	<i>Display only.</i> When the <u>Profile PIN</u> was last changed.	MM/DD/YYYY hh:mm
ODXLatTableNum	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
MaxImmedMtgsPerDay	See <u>Scheduling restriction (meetings to start within 6 hours of scheduling)</u> .	<ul style="list-style-type: none"> <li>• Numeric-range is 0 to 50</li> <li>• 10000-Unrestricted*</li> <li>• 10001-Cannot schedule</li> <li>• gd</li> </ul>
DayOfLastImmedMtg	<i>Display only.</i> The date and time of the last immediate meeting that this user scheduled.	MM/DD/YYYY hh:mm
NumImmedMtgsOnThatDay	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>0</b> .	-
MaximumMeetingLength	See <u>Maximum meeting length (minutes)</u> .	gd/Numeric-range is 0 to 1440

Table: Import and Export Data Specifications for User Profiles

	Import restriction: This cannot exceed the value of the <u>Maximum meeting length (minutes)</u> field on the <u>Meeting Configuration Page</u> .	
MaxVUIODsPerMtg	See <u>Maximum TUI dial-out attempts per meeting</u> .	<ul style="list-style-type: none"> <li>• Numeric-range is 0 to 500</li> <li>• 10000-Unrestricted*gd</li> </ul>
faxnum	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, leave this field blank.</p>	-
pgrnum	See <u>Pager number</u> .	0 to 32 alphanumeric characters
mxattsprmtg	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
rcvnotifs	See <u>Can receive notifications</u> .	Yes/No/gd
attnprf	See <u>Method of attending</u> .	UserCallsIn/SysFindsUser
prmrynotifprf	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
altnotifprf		
pgrtype	See <u>Pager type</u> .	DIDPager/NonDIDPager
emailtype	<p>See <u>Email type and format</u>, which combines the <u>emailtype</u> and <u>EmailFormat</u> fields.</p> <p>Import restriction: The <u>emailtype</u> value determines which options are supported in the <u>EmailFormat</u> field.</p>	SMTP/Exchange/LotusNotes/gd
site	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
preferredunit	<p>See <u>Schedule home server</u>.</p> <p>Import restriction: Cisco Unified MeetingPlace</p>	Numeric-range is 0 to 999/gd

Table: Import and Export Data Specifications for User Profiles

	Release 8.0 supports a smaller range of values than earlier releases. If you import user profiles that were originally configured for an earlier release system, make sure that you adjust this value accordingly.	
emailaddr	See <u>Email address</u> .	0 to 128 alphanumeric characters
faxlattblnum	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
sndnotifs	See <u>Can send notifications</u> .	Yes/No/gd
autodistatts	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>No</b> .	-
dfltnotifprio	See <u>Priority</u> .	Low/Normal/Urgent/gd
sndnotifonmtgch	See <u>Send if meeting changes</u> .	Yes/No/gd
sndinvlstwnotif	See <u>Include invitee list when scheduled from web</u> .	Yes/No/gd
sndmtgpwdwnotif	See <u>Include meeting password</u> .	Yes/No/gd
rcvattswnotif	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
playattlstfifo	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
autostrtrcrd	See <u>Auto-start recording</u> .	Yes/No/gd
disablerollcall	See <u>Disable roll call</u> .	Yes/No/gd
schedhomesiteonly	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
concurrentquestions	<i>Not supported.</i>  Import requirement: Do not modify this field from the exported value. If you import a new	-

Table: Import and Export Data Specifications for User Profiles

	profile, enter <b>0</b> .	
announceqarr	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>gd</b>.</p>	
announceqdep	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	
fqnadisable	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	
ftellpartpos	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	
fadvanceinfo	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	
fautoproenabled	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	
fstartpeopleinwr	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new group, enter <b>gd</b>.</p>	
publiculallowed	<p><i>Not supported.</i></p>	
groupulallowed	<p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	
privateulallowed		
meetingcategory	See <u>Default meeting category</u> .	

Table: Import and Export Data Specifications for User Profiles

		0 to 20 alphanumeric characters/gd
numdataparts	<i>Not supported.</i>	
chatclienttype	Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
fallowdataconf	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
fchatsession	<i>Not supported.</i>	
fismtgseminartype	Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
fallowguestview	See <u>Show meetings in public listing</u> .	Yes/No/gd
qnanotify	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	-
InternetEmailAddr	<i>Not supported.</i> Import requirement: Do not modify this field from the exported value. If you import a new profile, leave this field blank.	-
EncryptedUserPWD or upwd	The exported <u>EncryptedUserPWD</u> field is the encrypted <u>User password</u> .  When importing a user profile:  <ul style="list-style-type: none"> <li>• Use the <u>EncryptedUserPWD</u> field to import a previously encrypted user password.</li> <li>• Use the import-only <u>upwd</u> field to import an unencrypted user password.</li> </ul> Import requirements:  <ul style="list-style-type: none"> <li>• The import file must contain the <u>EncryptedUserPWD</u> field or the <u>upwd</u> field. If both fields are included in the</li> </ul>	<ul style="list-style-type: none"> <li>• blank (no password; externally authenticated)</li> <li>• 5 to 45 alphanumeric characters</li> </ul>

Table: Import and Export Data Specifications for User Profiles



	<p>import file, one must be left blank in each user profile.</p> <ul style="list-style-type: none"> <li>• If the <u>isLocalUser</u> field is set to No, both the <u>EncryptedUserPWD</u> and <u>upwd</u> fields must be left blank.</li> </ul> <p>Import restrictions:</p> <ul style="list-style-type: none"> <li>• Unicode is not supported.</li> <li>• If the user is authenticated by an external directory, you cannot modify the <u>User password</u> through Cisco Unified MeetingPlace.</li> </ul> <p>See <u>External AXL Authentication for Directory Service Users</u> in the <u>Configuring Cisco Unified MeetingPlace Directory Service</u> module.</p>	
<p>EncryptedProfilePWD  or  prfpwd</p>	<p>The exported <u>EncryptedProfilePWD</u> field is the encrypted <u>Profile PIN</u>.</p> <p>When importing a user profile:</p> <ul style="list-style-type: none"> <li>• Use the <u>EncryptedProfilePWD</u> field to import a previously imported profile PIN.</li> <li>• Use the import-only <u>prfpwd</u> field to import an unencrypted profile PIN.</li> </ul> <p>Import requirements:</p> <ul style="list-style-type: none"> <li>• The import file must contain the <u>EncryptedProfilePWD</u> field or the <u>prfpwd</u> field. If both fields are included in the import file, one must be left blank in each user profile.</li> <li>• If the <u>isLocalUser</u> field is set to No, both the <u>EncryptedProfilePWD</u> and <u>prfpwd</u> fields must be left blank.</li> </ul> <p>Import restrictions:</p> <ul style="list-style-type: none"> <li>• This field cannot be modified in the preconfigured <u>Guest Profile</u>.</li> <li>• If the user is authenticated by an external directory, you cannot modify the <u>Cisco Unified MeetingPlace Release 8.0 -- Administration Center</u></li> </ul>	<ul style="list-style-type: none"> <li>• blank (no password; authenticated externally)</li> <li>• 5 to 45 alphanumeric characters</li> </ul>

Table: Import and Export Data Specifications for User Profiles

	<p><u>Page References for Cisco Unified MeetingPlace (A - C pages)#Table: Field Reference: Add User Profile Page and Edit User Profile PageProfile PIN through Cisco Unified MeetingPlace.</u></p> <p>See <u>External AXL Authentication for Directory Service Users in the Configuring Cisco Unified MeetingPlace Directory Service module.</u></p>	
fCanInviteRemoteServers	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
altpnum	See <u>Alternate phone number.</u>	<p>0 to 32 characters of the following types:</p> <ul style="list-style-type: none"> <li>• numeric</li> <li>• (),-.</li> <li>• space ( )</li> </ul>
1stSearch		
2ndSearch	See <u>Search order for find me.</u>	Main phone/Alternate phone/ Pager
3rdSearch		
canallowguestoutdial	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
allowguestoutdial		
VLanguage	See <u>Language.</u>	0 to 128 alphanumeric characters/gd
fEndMtgWarn	<i>Not supported.</i>	-
fMtgExtendPrompts	Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b> .	
SSI_SystemID		
SSI_RollMapID		

Table: Import and Export Data Specifications for User Profiles

SSI_SiteID		
CanChangeMtgID	See <u>Can change meeting ID via phone.</u>	Yes/No/gd
RsvnlessCnfg	See <u>Use reservationless.</u>	<ul style="list-style-type: none"> <li>• 0-Yes</li> <li>• 1-No* gd</li> </ul>
RsvnlessCnfgGD	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>255</b>.</p>	-
AllowVideoSched	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
AllowInternetAccess	See <u>Allow Internet access.</u>	Yes/No/gd
VideoEndPtBandwidth	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
bountyUser	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>TRUE</b>.</p>	-
isLocalUser	<p>Whether the user profile is for a Directory Service user. Also determines the user authentication method:</p> <ul style="list-style-type: none"> <li>• <u>Yes</u>-Local authentication against the Cisco Unified MeetingPlace database.</li> <li>• <u>No</u>-Directory Service user; External AXL authentication.</li> </ul> <p>See <u>Directory Service isLocalUser Setting In User Profiles</u> in the <u>Configuring Cisco Unified MeetingPlace Directory Service</u> module.</p> <p>Restriction: This field does not appear in the Administration Center. You can view this setting only by exporting user profiles, and you can modify this field only through a manual import process.</p>	Yes/No
EmailFormat		txt/html/RTF/gd

Table: Import and Export Data Specifications for User Profiles

	<p>See <a href="#">Email type and format</a>, which combines the <a href="#">emailtype</a> and <a href="#">EmailFormat</a> fields.</p> <p><b>Note:</b> If you use the <a href="#">gd</a> value, make sure that the <a href="#">EmailFormat</a> field in the assigned user group is compatible with the <a href="#">emailtype</a> field in the user profile.</p> <p>Only the following combinations of <a href="#">emailtype</a> and <a href="#">EmailFormat</a> fields are supported:</p> <ul style="list-style-type: none"> <li>• SMTP/html</li> <li>• SMTP/txt</li> <li>• LotusNotes/txt</li> <li>• Exchange/html</li> <li>• Exchange/txt</li> </ul>	
ReserveVoiceLicenses	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
LockedProfileTime	<p>Time when profile was locked, in seconds, from 1/1/1970 00:00:00 GMT.(2)</p> <p>A value of 0 means that the profile is not currently locked.</p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>0</b> for this field.</p>	Integer-range is 0 to 2 <sup>31</sup> - 1
CanReserveVideoPorts	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
PreferVideo		
PreferDataConf	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>Yes</b>.</p>	-
FRsvnlessAllowInternetAcc	See <a href="#">Reservationless allow Internet access</a> .	Yes/No/gd
attendMode	See <a href="#">Auto attend mode</a> .	<ul style="list-style-type: none"> <li>• 0-None</li> <li>• 1-Automatically join meeting*</li> </ul>

Table: Import and Export Data Specifications for User Profiles

		<ul style="list-style-type: none"> <li>2-Automatically sign in</li> <li>• gd</li> </ul>
attendPasswdRequired	See <a href="#">Auto attend requires profile PIN</a> .	Yes/No/gd
videoTypes	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
mtgEntryMode	See <a href="#">Meeting entry mode</a> .	<ul style="list-style-type: none"> <li>• 0-Echo meeting</li> <li>• 1-Skip ID repeat*</li> <li>• 3-Skip ID repeat and skip names</li> <li>• gd</li> </ul>
dataConfClientType	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
CCMpkid	<p>This field determines whether the user profile will be affected by the next <a href="#">Directory Service</a> user profile update.</p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, leave this field blank.</p>	Up to 40 characters

Footnote 1: gd = group default

Footnote 2: GMT = Greenwich Mean Time

#### Related Topics

- [Exporting User Profiles in the Running Reports and Exporting Data from Cisco Unified MeetingPlace](#) module
- [Adding or Editing User Profiles by Import in the Importing Data into Cisco Unified MeetingPlace](#) module
- [Deleting User Profiles by Import in the Importing Data into Cisco Unified MeetingPlace](#) module

## Video Terminal Profiles-Raw Data Export and Import Specifications

**Table: Import and Export Data Specifications for Video Terminal Profiles**

Field Name	Description	Size and Type of Value
videoTermName	See <u>Video terminal name</u> .  Import requirement: This field is required when you add VTPs by import.	0 to 32 alphanumeric characters
videoTermId	Unique value that identifies the VTP in report and export output.  For VTPs that you manually add through the Administration Center, this value is automatically generated by the system.  Import requirements: <ul style="list-style-type: none"> <li>• This field is required whether you are adding or deleting VTPs by import.</li> <li>• Do not modify this field from the exported value.</li> </ul>	1 to 30 numeric characters
videoEndPtAddStr	See <u>Endpoint E.164 number</u> .  Import requirement: This field is required when you add VTPs by import.  Restriction: Only the following characters are allowed: (),-, and 0-9.	Up to 32 characters
grpname	See <u>Group name</u> .  Import requirements: <ul style="list-style-type: none"> <li>• This field is required whether you are adding or deleting user profiles by import.</li> <li>• Do not modify this field from the exported value. If you import a new VTP, enter <b>System</b>.</li> </ul>	1 to 17 alphanumeric characters
grpnum	<u>Number</u> of user group.  Import requirement: Do not modify this field from the exported value. If you import a new VTP, enter <b>0</b> to indicate the <u>System User Group</u> .	0 to 17 numeric characters
emailaddr	See <u>Email address</u> .	0 to 128 alphanumeric characters
tzcode	<u>Time zone</u> of the video terminal.	0 to 17 ASCII text characters

	<p>Import requirements:</p> <ul style="list-style-type: none"> <li>• The integer value in the import file must match a value defined by Cisco Unified MeetingPlace. Make sure you use a previously exported value.</li> <li>• If the import file contains the <u>tzcode</u> header field, all user groups in the import file must have a valid entry for the field. For any invalid or blank <u>tzcode</u> values, the associated user group is not imported, and an error is logged.</li> </ul>	
supportSIPReInvite	See <u>Skip meeting entry voice prompts for dial-out calls.</u>	Yes/No
attndprf	See <u>Method of attending.</u>	UserCallsIn/SysFindsUser
rcvnotifs	See <u>Can receive notifications.</u>	Yes/No/gd(1)
rcvattswnotif	<p><i>Not supported.</i></p> <p>Import requirement: Do not modify this field from the exported value. If you import a new profile, enter <b>gd</b>.</p>	-
preferedCodec	<p>See <u>Video terminal codec.</u></p> <ul style="list-style-type: none"> <li>• 1-H.261</li> <li>• 2-H.263</li> <li>• 5-H.264</li> <li>• 6-Use default (H.264)</li> </ul>	1/2/5/6

Footnote 1: gd = group default

**Related Topics**

- [Exporting Video Terminal Profiles in the Running Reports and Exporting Data from Cisco Unified MeetingPlace module](#)
- [Adding or Editing Video Terminal Profiles by Import in the Importing Data into Cisco Unified MeetingPlace module](#)
- [Deleting Video Terminal Profiles by Import in the Importing Data into Cisco Unified MeetingPlace module](#)

## Meetings-Raw Data Export and Import Specifications

**Note:** The first line in the export file specifies the Cisco Unified MeetingPlace version. If you want to import this file or use this file as a template for importing data, you must *not* modify this line.

**Table: Import and Export Data Specifications for Meetings**

Field Name	Description	Size and Type of Value
ConfNum		1 to 9 numeric characters

	Unique conference number assigned to this meeting after it was successfully scheduled.  Import requirement: Must be a unique value.	
StartDateTimeOfConf	The date and time for which this meeting is scheduled.	MM/DD/YYYY HH:MM
SchedulerUid	<u>User ID</u> of the meeting owner.  Import requirement: Must be a valid <u>User ID</u> .	0 to 17 alphanumeric characters
ContactUid	<u>User ID of delegate</u> of the meeting owner.  Import requirement: Must be a valid <u>User ID</u> .	0 to 17 alphanumeric characters
DialableConfID	Meeting ID.	0 to 9 ASCII text characters
LastModified	Date and time when the meeting information was last modified.	MM/DD/YYYY HH:MM
OriginallyScheduled	Date and time when this meeting was originally scheduled.	MM/DD/YYYY HH:MM
PartRecordTimeUsed	Amount of time, in seconds, of participant name recordings.	1 to 9 numeric characters
NameRecordTimeUsed	Amount of time, in seconds, of the recorded meeting name.	1 to 9 numeric characters
AgendaRecordTimeUsed	Amount of time, in seconds, of the meeting agenda recording.	1 to 9 numeric characters
VRecordRecordTimeUsed	Amount of time, in seconds, of the meeting recording.	1 to 9 numeric characters
VIntroTimeUsedSecs	Amount of time, in seconds, of the meeting introduction recording.	1 to 9 numeric characters
TName	Meeting subject.	0 to 63 alphanumeric characters
SchedulerTimeZone	<u>Time zone</u> of the meeting scheduler.  Import requirement: The integer value in the import file must match a value defined by Cisco Unified MeetingPlace. Make sure you use a previously exported value.	0 to 17 ASCII text characters
TAgenda	<i>Not supported.</i>	-
VName	Whether the meeting name was recorded.	Recorded/Not Recorded
VAgenda	Whether the meeting agenda was recorded.	Recorded/Not Recorded

Table: Import and Export Data Specifications for Meetings



VRecord	Whether the meeting was recorded.	Recorded/Not Recorded
VMeetingIntro	Whether the meeting introduction was recorded.	Recorded/Not Recorded
VoiceStorageEndTime	<p>When the following items for this meeting will be deleted from the Application Server:</p> <ul style="list-style-type: none"> <li>• Voice agenda</li> <li>• Conference name</li> <li>• Meeting introduction</li> <li>• Voice recording</li> <li>• Attachment records</li> <li>• Recorded participant names</li> <li>• Voice storage reservation</li> </ul> <p>This date cannot be changed, and it is set to 7 days after the meeting ends.</p>	MM/DD/YYYY HH:MM
ActSrtTimeOfConf	When the meeting started.	<p>MM/DD/YYYY HH:MM</p> <p><b>Note:</b> If meeting was not attended, field displays time zero (midnight January 1, 1970 converted to server's time zone).</p>
TotConfPortSec	<p>Accumulated number of seconds for all voice ports that were in the meeting.</p> <p>For example, if three ports were in the meeting for 5, 6, and 7 seconds, respectively, then TotConfPortSec = 5 + 6 + 7 = 18.</p>	1 to 9 numeric characters
ActLenOfConf	Actual length of the meeting, in minutes.	1 to 9 numeric characters
nPartRegistered	Number of users that were either invited to or joined the meeting.	1 to 4 numeric characters
ActnParticipants	Number of users who attended this meeting.	1 to 4 numeric characters
PeakNumberOfParticipants	Peak number of participants in this meeting.	1 to 4 numeric characters
PeakNumberOfPorts	Peak number of voice ports used during this meeting.	1 to 4 numeric characters
OrigNumberOfPorts	Number of voice ports planned for this meeting.	1 to 4 numeric characters
nPartAttemptsAfterConfLocked	The number of participants that tried to join the meeting after it was locked.	1 to 4 numeric characters
ReqLengthOfConf	The requested number of minutes for this meeting.	1 to 4 numeric characters
nPortsRequired	The number of voice ports required for this meeting.	1 to 4 numeric characters

Table: Import and Export Data Specifications for Meetings

nPartsRequested	The number of participants invited to the meeting.	1 to 4 numeric characters
MaxDaysReOccurring	Number of instances of reoccurrence.  For example, a meeting that occurs monthly for 2 years will have a value of 12.	1 to 9 numeric characters
MeetingJoinRestriction	Who can join the meeting.	Anyone/Users/Invited Users/ None
DefaultAbility	TUI (1) abilities of uninvited participants upon entering the meeting.  For information about the values, see the <a href="#">SpeakingAbility</a> meeting participant information field.  Previous releases of Cisco Unified MeetingPlace supported other speaking abilities. If you import any of these old values, the system will treat them as SPEAKERPLUS.	SPEAKER/SPEAKERPLUS
ReOccurringConference	Frequency of meeting recurrence.  A value of PERMANENT refers to a continuous meeting.	ONCE/DAILY/WEEKLY/ MONTHLY/WEEKDAYS/ PERMANENT/BIWEEKLY/ MONTHLYBYDAYOFWEEK1/ MONTHLYBYDAYOFWEEK2/ MONTHLYBYDAYOFWEEK3/ MONTHLYBYDAYOFWEEK4/ MONTHLYBYDAYOFWEEKLAST/ SPECIFIEDWEEKDAYS
MtgNoteRestriction	<i>Not supported.</i>	-
fPasswordRequired	Whether the meeting requires a password.	Yes/No
fNamedIntroduction	Announcement played when participants join the meeting.	Beep/BeepName/None
fNamedDisconnect	Announcement played when participants leave the meeting.	Beep/BeepName/None
fScreenedIntroduction	<i>Not supported.</i>	-
fRecordConference	Whether this meeting is recorded.	Yes/No
fPosted	Whether the recording of this meeting is posted.	Yes/No
fQuickMtgEntryAllowed	<i>Not supported.</i>	-
fPasswordRequiredOnOD	Whether dial-out participants must enter <a href="#">Profile PINs</a> before being admitted into the voice meeting.	Yes/No
nUserVUIMtgNotesAccesses	<i>Not supported.</i>	-
nUserGUIMtgNotesAccesses	<i>Not supported.</i>	-

Table: Import and Export Data Specifications for Meetings

nGuestMtgNotesAccesses	<i>Not supported.</i>	-
SchedulingClient	<i>Not supported.</i>	-
CurAttRefID	<i>Not supported.</i>	-
CurNumDataAtt	<i>Not supported.</i>	-
CurNumVoiceAtt	<i>Not supported.</i>	-
CurVoiceAttSpace	<i>Not supported.</i>	-
CurDataAttSpace	<i>Not supported.</i>	-
nVoiceAttAdded	<i>Not supported.</i>	-
nDataAttAdded	<i>Not supported.</i>	-
PeaknVoiceAtt	<i>Not supported.</i>	-
PeaknDataAtt	<i>Not supported.</i>	-
PeakAttVoiceSpace	<i>Not supported.</i>	-
PeakAttDataSpace	<i>Not supported.</i>	-
CurAttNameHeaderSpace	<i>Not supported.</i>	-
MaxAttachments	<i>Not supported.</i>	-
fBAgendaAttAvail	<i>Not supported.</i>	-
fAutoStartRecord	Whether the system automatically starts recording the meeting.	Yes/No
fDisableRollCall	<i>Not supported.</i>	-
SendNotAboutMtgs	Whether an email notification was sent when this meeting was scheduled.  Notifications are never sent for reservationless meetings.	Yes/No
AutoDistributeAtt	<i>Not supported.</i>	-
DefNotPriority	Priority given to the email notifications sent when this meeting is scheduled.	Low/Normal/Urgent
SendNotAboutMtgChngs	Whether email notifications are sent when the following meeting parameters change:  <ul style="list-style-type: none"> <li>• Date or time</li> <li>• Password</li> <li>• Meeting ID</li> <li>• List of invitees</li> </ul>	Yes/No
SendInviteListWithNot	Whether to include a list of meeting invitees in email notifications for this meeting.	Yes/No
SendMtgPwdWithNot	Whether to include the meeting password in email notifications for this meeting.	Yes/No
fUsedBlastOutdial	Whether the system dials out to <i>all</i> meeting invitees.	Yes/No
BillCode	<u>Billing code</u> applied to this meeting.	0 to 18 alphanumeric characters
fTAgendaAttAvail	<i>Not supported.</i>	-
fVAgendaAttAvail	<i>Not supported.</i>	-

Table: Import and Export Data Specifications for Meetings

PriUnitNum	<i>Not supported.</i>	-
PriSiteNum	<i>Not supported.</i>	-
concurrentquestions	<i>Not supported.</i>	-
announceqarr	<i>Not supported.</i>	-
announceqdep	<i>Not supported.</i>	-
fqnadisabled	<i>Not supported.</i>	-
fautoproenabled	<i>Not supported.</i>	-
fstartpeopleinwr	<i>Not supported.</i>	-
numdataparts	<i>Not supported.</i>	-
fchatsession	<i>Not supported.</i>	-
fismtgseminartype	<i>Not supported.</i>	-
fallowguestview	Whether this meeting is publicly listed in the Cisco Unified MeetingPlace web user portal.	Yes/No
tottimesfgiven	<i>Not supported.</i>	-
qnanotify	<i>Not supported.</i>	-
PeakVRecordTimeUsed	Peak number of recording seconds used by a meeting over its lifetime. A historical statistic used for billing purposes.	1 to 9 numeric characters
MPCConnectionType	<i>Not supported.</i>	-
nRemoteServersRegistered	<i>Not supported.</i>	-
TotnRSsInvited	<i>Not supported.</i>	-
ActnRSs	<i>Not supported.</i>	-
PeakNumberOfRSs	<i>Not supported.</i>	-
allowguestoutdial	Whether guest users can dial out from this meeting.	Yes/No
TotDCCConfPortSec	Total number of seconds that the web meeting room was used by this meeting.	1 to 9 numeric characters
VLanguage	Meeting language, which is used for voice prompts that are heard by <i>all</i> meeting participants.	0 to 128 alphanumeric characters
EncryptedConfPwd	Encrypted meeting password.	0 to 17 alphanumeric characters
StartDateTimeOfConfGMT	Date on which the meeting is scheduled to occur.	MM/DD/YYYY
fEndMtgWarn	Whether the end-of-meeting announcement is played in this meeting.	Yes/No
fMtgExtendPrompts	Whether meeting-extension announcements are played in this meeting.	Yes/No
ActSrtTimeOfDataConf	Date and time at which the web meeting room meeting started.  <b>Note:</b> If this is a voice-only meeting (no web meeting room), this field displays a dummy value.	MM/DD/YYYY HH:MM

Table: Import and Export Data Specifications for Meetings

ActLenOfDataConf	The actual length of the web meeting, in minutes.	1 to 9 numeric characters
ConfExtensionFailCode	Failure code that indicates why an attempted meeting extension failed. See <a href="#">Table: Failure Code Reference: Scheduling Failures Information</a> .  If there were no attempts to extend the meeting, then this value is 0.	1 to 6 numeric characters
NumSuccConfExtensions	Number of times that the meeting was successfully extended.	1 to 9 numeric characters
MeetingType	Descriptor for meetings.  <ul style="list-style-type: none"> <li>• 0-Scheduled</li> <li>• 1-Reservationless</li> <li>• 2-Reserve All Ports (RAP)</li> <li>• 3-Not supported</li> <li>• 4-Web only</li> </ul>	Numeric-range is 0 to 4
RsvnlessStartID	<u>User ID</u> of the person who initiates the reservationless meeting.  This field applies only to reservationless meetings.	0 to 17 alphanumeric characters
OutdialFirstCall	Whether the system dials out to all invitees after the first person joins the meeting.  This field applies only to continuous meetings, which can be scheduled only by system administrators.	Yes/No
nVideoPortsReq	The number of video ports required for this meeting.  Import restriction: This value cannot exceed the number of licensed ports.	1 to 4 numeric characters
ActNumVideoPorts	Number of video participants in this meeting.	1 to 4 numeric characters
TotVideoPortSecs	Total number of seconds that video endpoints were in the meeting.  For example, if three video endpoints attended the meeting for 5, 6, and 7 seconds, respectively, then $TotVideoPortSec = 5 + 6 + 7 = 18$ .	1 to 9 numeric characters
AllowInternetAccess	Whether the meeting is accessible by anyone on the Internet and appears on	Yes/No

Table: Import and Export Data Specifications for Meetings

	the external Web Server.	
nDCPortsRequired	Number of web ports required for this meeting to be scheduled.  Import restriction: This value cannot exceed the number of licensed ports.	1 to 4 numeric characters
meetingInvitees	List of <u>User IDs</u> or email addresses of meeting invitees, separated by a semicolon (;).  Example: user1;user2@example.com;user3;user4  Import restriction: The number of invitees cannot exceed the value in the <u>Maximum ports per scheduled meeting</u> field.	Alphanumeric characters
allowVideoConf	Whether video is enabled for this meeting.	Yes/No
external	Identical to <u>AllowInternetAccess</u> .	Yes/No
videoTypeId		
videoTypeName		
videoMinBitRate	<i>Not supported.</i>	-
videoMaxBitRate		
videoCodec		
OrigNvideoPorts	Number of originally scheduled video ports.	1 to 4 numeric characters
fMeetingTemplateID	<i>Not supported.</i>	-
fWebOnly	Whether participants are allowed to enter only the web meeting room (no audio participants).	Yes/No
fAllowAnyoneToView	Whether anyone can search to find this meeting through the web user portal.  If set to No, then even system administrators will not be able to see the meeting.	Yes/No

Table: Import and Export Data Specifications for Meetings

Footnote 1: TUI = telephone user interface

#### Related Topics

- [Exporting Meetings](#) in the [Running Reports and Exporting Data from Cisco Unified MeetingPlace](#) module
- [Scheduling Meetings by Import](#) in the [Importing Data into Cisco Unified MeetingPlace](#) module
- [Canceling Meetings by Import](#) in the [Importing Data into Cisco Unified MeetingPlace](#) module

## Outgoing Calls Information-Raw Data Export Specifications

Table: Export Data Specifications-Outgoing Calls Information

Field Name	Description	Size and Type of Value
StartTimeOfCall	Date and time when the system placed the call.	MM/DD/YYYY HH:MM
uid	<u>User ID</u> of the person who initiated the dial-out call.	1 to 30 alphanumeric characters
ConfNum	See <u>ConfNum</u> .	1 to 9 numeric characters
nSeconds	Duration of the outgoing call, in seconds.	An unsigned integer
CalledDest	Phone number that was dialed.	No more than 32 ASCII digits
fBlastOutdial	Whether this was a blast dial-out call.	Yes/No
UpdateTime	When this record was most recently updated.	MM/DD/YY HH:MM
PartID	<p>Unique number that identifies each meeting participant. The meeting owner is assigned the number 0. The first non-owner participant is assigned the number 1. As each participant joins, the next incremental number is assigned.</p> <p>If a profiled user leaves and rejoins a meeting, the same PartID is used. If a guest user leaves and rejoins a meeting, a new PartID is used.</p> <p>A PartID of -851969 indicates that the user did not actually join the meeting.</p>	0 to 17 ASCII text characters

#### Related Topics

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace](#) module

## Meeting Participant Information-Raw Data Export Specifications

Table: Export Data Specifications-Meeting Participant Information

Field Name	Description	Size and Type of Value
PartId	See <u>PartID</u> .	0 to 17 ASCII text characters
ConfNum	See <u>ConfNum</u> .	1 to 9 numeric characters
uid	<u>User ID</u> of the meeting participant.	1 to 30 alphanumeric characters
MeetingId	Meeting ID.	Numeric characters
StartTimeOfConf	Date and time when the meeting started.	MM/DD/YYYY hh:mm
nVSecInConf	Amount of time, in seconds, that the participant spent in the voice portion of the meeting.	An unsigned integer
nWFSecInConf	<i>Not supported.</i>	-
nSecsOutboundCalls	Amount of time, in seconds, that the participant spent in a call that was dialed out by the system.	An unsigned integer
VNameHeader	Whether the name of the participant was recorded.	Recorded/Not_Recorded
nOutboundCalls	Number of dial-out calls initiated by this participant	An unsigned integer
nRetries	Number of dial-out retries initiated by this participant	An unsigned integer
TNameHeader	<p><u>First name</u> and <u>Last name</u> of the meeting participant.</p> <p>For unprofiled participants, this displays one of the following:</p> <ul style="list-style-type: none"> <li>Name the guest user enters to join the meeting from the Cisco Unified MeetingPlace web user portal.</li> <li>"Guest User" followed by the phone number or extension from which the user dials in.</li> </ul>	0 to 64 alphanumeric characters
SpeakingAbility	<p>TUI (1) abilities of the participant upon leaving the meeting.</p> <p>Upon entering the meeting, the participant has one of the following sets of abilities:</p> <ul style="list-style-type: none"> <li>SPEAKER-Depending on user profile parameters, may be able to place dial-out calls or start recordings.</li> <li>SPEAKERPLUS-In addition to the SPEAKER abilities, has meeting control, including the ability to lock the meeting and to admit or remove participants.</li> </ul>	<ul style="list-style-type: none"> <li>SPEAKER</li> <li>SPEAKERPLUS*</li> <li>MUTED_SPEAKER</li> <li>MUTED_SPEAKERPLUS</li> </ul>
nVUIODsMade	Number of dial-out calls that this participant initiated from the TUI.	An unsigned integer
nTimesQAsked	Number of times a question was asked by the participant.	An unsigned integer
nTimesFGiven	<i>Not supported.</i>	-



UpdateTime	When this record was most recently updated.	MM/DD/YYYY hh:mm
nDCSecInConf	Amount of time, in seconds, that the user spent in the web meeting room.	An unsigned integer
nSecInMTGNotes	Amount of time, in seconds, that the user spent listening to recordings and other notes for this meeting.	An unsigned integer

Footnote 1: TUI = telephone user interface

#### Related Topics

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace module](#)

## Meeting Participant Join Leave Information-Raw Data Export Specifications

**Note:** This report provides a separate entry for each Device used by a meeting participant

**Table: Export Data Specifications-Meeting Participant Join Leave Information**

Field	Description	Size and Type of Value
PartID	See <u>PartID</u> .	0 to 17 ASCII text characters
UserID	<u>User ID</u> of the meeting participant.	1 to 30 alphanumeric characters
ConfNum	See <u>ConfNum</u> .	1 to 9 numeric characters
MeetingID	Meeting ID.	
gmStartDate	Date on which the user joined the meeting.	MM/DD/YYYY
gmStartTime	Time at which the user joined the meeting.	HH:MM:SS AM/PM
gmEndDate	Date on which the user left the meeting.	MM/DD/YYYY
gmEndTime	Time at which the user left the meeting.	HH:MM:SS AM/PM
Device	Device identifier or port number: <ul style="list-style-type: none"> <li>• 0 to 1151-voice port</li> <li>• 4080-MeetingPlace Conference Manager</li> <li>• 4081-Web conferencing</li> <li>• 4082-Share pod in web meeting</li> <li>• 4084-Cisco Unified MeetingPlace Video</li> </ul>	<ul style="list-style-type: none"> <li>• 0 to 1151</li> <li>• 4080 to 4084</li> </ul>
nIncDigits	Number of DNIS digits that were received from the PBX.	An unsigned integer
IncDigits	String of DNIS digits received from the PBX.	Numerical string of up to 24 digits
AttachmentID	<i>Not supported.</i>	-
nANIDigits	Number of ANI digits that were received from the PBX.	An unsigned integer
ANIDigits	String of ANI digits received from the PBX.	Numerical string of up to 24 digits

**Related Topics**

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace module](#)

**Scheduling Failures Information-Raw Data Export Specifications**

- [Table: Export Data Specifications-Scheduling Failures Information](#)
- [Table: Failure Code Reference: Scheduling Failures Information](#)

**Table: Export Data Specifications-Scheduling Failures Information**

<b>Field</b>	<b>Description</b>	<b>Size and Type of Value</b>
SchedulerUid	<u>User ID</u> of the meeting owner.	1 to 30 alphanumeric characters
SchedulingTime	Date and time when the user tried to schedule the meeting.	MM/DD/YYYY hh:mm
MtgStartTime	Date and time that the user requested for the meeting to begin.	MM/DD/YYYY hh:mm
DialableConfID	Meeting ID.	0 to 9 ASCII text characters
NumOfPortsRqsted	Number of voice ports requested for the failed meeting.	An unsigned integer
MtgLenthInMin	Number of minutes that the user requested for the meeting length.	An unsigned integer
FailCode	Failure code that describes why the meeting could not be scheduled. See <a href="#">Table: Failure Code Reference: Scheduling Failures Information</a> .	An unsigned integer
ErrorString	A text string message that is displayed to the user. This message corresponds to the <a href="#">FailCode</a> .	An unsigned integer
FailSeqNum	Tracks multiple failure attempts for the same meeting.	An unsigned integer
UniqueConfNum	Unique conference number assigned to this meeting after it was successfully scheduled. This is 0 for meetings that are not scheduled successfully.	An unsigned integer

**Table: Failure Code Reference: Scheduling Failures Information**

<b>Field</b>	<b>Description</b>
5122	Generic code for any error found from internal reservation mechanism.
5129	Original resource reservation cannot be found.
5154	The server cannot commit the extensions because of a failure to save the extension record to the database.
5155	Server did not extend meeting because of one of these reasons: <ul style="list-style-type: none"> <li>• Less than two participants were in the voice and web sessions.</li> <li>• The meeting was extended to more than 24 hours.</li> </ul>

	<ul style="list-style-type: none"> <li>• The Extend Meeting parameter was set to 0 minutes.</li> </ul>
5190	The Meeting ID conflicts with an existing meeting.
5209	The meeting was terminated.
5291	There were not enough video resources.
5295	Not enough ports are available.
5318	The meeting could not be scheduled because the recording would have been too long.
131158	One person remains in the meeting.
131159	Meeting was extended more than 24 hours.
131262	Failed to extend because of meeting ID conflict.
131198	Failed to extend because of lack of voice ports.
131199	Failed to extend because of lack of recording space.

**Related Topics**

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace module](#)

## Scheduling Statistics Information-Raw Data Export Specifications

**Table: Export Data Specifications-Scheduling Statistics Information**

Header Field	Description	Size and Type of Value
fNumSchedSuccesses	Number of scheduling operations that were successful.  For example, suppose that a user successfully schedules a recurring meeting with 100 instances from the Cisco Unified MeetingPlace web user portal. This would add 1 to <u>fNumSchedSuccesses</u> and 100 to <u>fNumSchedWeb</u> .	Up to 16 numeric integers
fNumSchedWindows	Number of meetings scheduled from Microsoft Windows computers.	Up to 16 numeric integers
fNumSchedMac	Number of meetings scheduled from Macintosh computers.	Up to 16 numeric integers
fNumSchedNotes	Number of meeting scheduled from IBM Lotus Notes.	Up to 16 numeric integers
fNumSchedVUI	Number of meetings scheduled from the TUI.	Up to 16 numeric integers
fNumSchedWeb	Number of meetings scheduled from the Cisco Unified MeetingPlace web user portal.	Up to 16 numeric integers
fSumSchedClients		

	Total number of meetings that were successfully scheduled, specifically, the sum of these values: <u>fNumSchedWindows</u> , <u>fNumSchedMac</u> , <u>fNumSchedNotes</u> , <u>fNumSchedVUI</u> , and <u>fNumSchedWeb</u> .	Up to 16 numeric integers
--	---	---------------------------

**Related Topics**

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace module](#)

## Scheduling Activity By User Information-Raw Data Export Specifications

**Table: Export Data Specifications-Scheduling Activity By User Information**

Header Field	Description	Size and Type of Value
dialableConfId	Meeting ID.	0 to 9 ASCII text characters
confname	Meeting subject.	0 to 63 alphanumeric characters
schedulerName	<u>First name</u> and <u>Last name</u> of the meeting scheduler.	0 to 64 alphanumeric characters
dateScheduled	Date when the user scheduled the meeting.	MM/DD/YYYY
timeScheduled	Time when the user scheduled the meeting.	hh:mm
conflength	Requested number of minutes for this meeting.	Numeric
nPortsRequired	Number of voice ports required for this meeting.	Numeric
groupIdNumber	<u>Number</u> of user group to which this user belongs.	1 to 17 alphanumeric characters
groupName	<u>Name</u> of user group to which this user belongs.	1 to 17 alphanumeric characters
userID	<u>User ID</u> of this user.	1 to 30 alphanumeric characters
videoPortsReserved	Whether video ports were reserved for each meeting,	Yes/No

**Related Topics**

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace module](#)

## Continuous Meetings Information-Raw Data Export Specifications

**Table: Export Data Specifications-Continuous Meetings Information**

Header Field	Description	Size and Type of Value
confnum	Unique conference number assigned to this meeting after it was successfully scheduled.	1 to 9 numeric characters
DialableConfID	Meeting ID.	0 to 9 ASCII text characters

ConfName	Meeting subject.	0 to 63 alphanumeric characters
organizerName	<u>First name</u> and <u>Last name</u> of the meeting owner.	0 to 64 alphanumeric characters
contactName	<u>User ID of delegate</u> that is assigned to the meeting owner.	1 to 30 alphanumeric characters
billCode	See <u>Billing code</u> .	0 to 17 alphanumeric characters
meetingType	See <u>MeetingType</u> .	Numeric-range is 0 to 4
startdatesched	Date on which the meeting is scheduled to begin.	MM/DD/YYYY
starttimesched	Time at which the meeting is scheduled to begin.	hh:mm
actnParticipants	The number of users who have attended this meeting.	Any numeric value
actlenofconf	Total number of seconds for which the continuous meeting had at least one participant.	1 to 9 numeric characters
recmins	<i>Not supported.</i>	-
peaknparticipants	Peak number of participants in this meeting.	Any numeric value
nUserVUIMtgNotesAccesses	Number of times that the meeting recordings and attachments have been accessed from the TUI.	Any numeric value
nGuestMtgNotesAccesses	Number of times that the meeting recordings and attachments have been accessed by guest users.	Any numeric value
nUserGUIMtgNotesAccesses	Number of times that the meeting recordings and attachments have been accessed from the Cisco Unified MeetingPlace web user portal.	Any numeric value
fconfportmins	Number of voice ports per minute used by the meeting.	Any numeric value
fdconfportmins	Number of web ports per minute used by the meeting.	Any numeric value
schedulerLastName	<u>Last name</u> of the meeting scheduler.	0 to 32 alphanumeric characters

#### Related Topics

- [Running Reports and Exporting Data from Cisco Unified MeetingPlace module](#)