

**Main page:** [Cisco Unity Express -- REST PI Service Operations](#)

**Previous page:** [Cisco Unity Express -- SMTP Server REST PI Service Operation](#)

**Next page:** [Cisco Unity Express -- Triggers REST PI Service Operation](#)

**Search the Cisco Unity Express documentation on the DocWiki:**

Loading

---


## Contents

- [1 User Defaults](#)
  - ◆ [1.1 Classes](#)
    - ◇ [1.1.1 UserDefaults](#)
    - ◇ [1.1.2 LockoutPolicy](#)
  - ◆ [1.2 Resources](#)

## User Defaults

### Classes

**Figure 22: User Defaults**



## UserDefaults

<b>Class Name</b>	UserDefaults		
<b>Extends From</b>	ManagedBaseElement		
<b>Description</b>	Class representing the default global password and PIN policy settings for all users.		
<b>XML Namespace</b>	http://userdefaults.model.rest.aesop.cisco.com		
<b>Field Name</b>	<b>Type</b>	<b>Constraints</b>	<b>Comments</b>
enableExpiry	Boolean		Enable or disable system-wide password or pin expiry
expiryDuration	Integer	Range 3-365	Maximum number of days for which subscribers'passwords or PIN are valid
historyDepth	Integer	Range 1-10	Specifies how many of a user's previous passwords or PIN are compared to the new value.
lockoutPolicy	LockoutPolicy		Specify whether subscribers are locked out permanently, or temporarily, when the maximum number of failed login attempts is reached.
minLength	Integer	Range for password is 3-32 Range for PIN is 3-16	Minimum length of password or PIN
permLockoutMaxFailures	Integer		Maximum number of failed attempts that will trigger a permanent lockout.
tmpLockoutAttempts	Integer		Initial number of failed attempts that will trigger a temporary lockout.
tmpLockoutDuration	Integer		Initial lockout duration for a temporary lockout (minutes).
tmpLockoutMaxFailures	Integer		Maximum number of failed attempts that will trigger a temporary lockout.

**LockoutPolicy**

<b>Class Name</b>	LockoutPolicy (Enumeration Class)
<b>Extends From</b>	
<b>Description</b>	Enumeration of lockout policy types
<b>XML Namespace</b>	http://license.model.rest.aesop.cisco.com
<b>Enum Values</b>	DISABLED PERMANENT TEMPORARY

**Resources**

<b>Resource URI</b>	<b>Operation</b>	<b>Input</b>	<b>Return Value</b>
/system/userdefaults/password	GET (Read user password related default values)		UserDefaults
	PUT (Update password related default values)	UserDefaults	
/system/userdefaults/pin	GET (Read user PIN default values)		UserDefaults
	PUT (Update default values for PIN )	UserDefaults	