

## Troubleshooting Alarms/Alerts to be sent as SNMP Traps

<b>Problem Summary</b>	The user is not able to send the alarms or alerts generated by the system as SNMP Traps.
<b>Error Message</b>	None.
<b>Possible Cause</b>	This may be caused either due to the incorrect SNMP configuration or incorrectly set MIB Trap parameters.
<b>Recommended Action</b>	<p>For sending the syslog messages as SNMP Traps, follow the below steps:</p> <ul style="list-style-type: none"> <li>• Set the SNMP Trap destination from the Cisco Unified Serviceability interface.</li> <li>• Enable trap generation in CISCO-SYSLOG-MIB. Set clogsNotificationEnabled (1.3.6.1.4.1.9.9.41.1.1.2) to true by using the SNMP Set operation</li> <li>• Set appropriate SysLog level in CISCO-SYSLOG-MIB. Set clogMaxSeverity (1.3.6.1.4.1.9.9.41.1.1.3) value by using the SNMP Set operation.</li> <li>• By default, the Alerts goes to local syslog. So, this will enable Alerts to be sent as SNMP Traps as well.</li> </ul>
<b>Release</b>	Release 8.0(1)
<b>Associated CDETS #</b>	None