

Troubleshooting Alarms/Alerts to be sent as SNMP Traps

| | |
|---------------------------|--|
| Problem Summary | The user is not able to send the alarms or alerts generated by the system as SNMP Traps. |
| Error Message | None. |
| Possible Cause | This may be caused either due to the incorrect SNMP configuration or incorrectly set MIB Trap parameters. |
| Recommended Action | <p>For sending the syslog messages as SNMP Traps, follow the below steps:</p> <ul style="list-style-type: none"> • Set the SNMP Trap destination from the Cisco Unified Serviceability interface. • Enable trap generation in CISCO-SYSLOG-MIB. Set clogsNotificationEnabled (1.3.6.1.4.1.9.9.41.1.1.2) to true by using the SNMP Set operation • Set appropriate SysLog level in CISCO-SYSLOG-MIB. Set clogMaxSeverity (1.3.6.1.4.1.9.9.41.1.1.3) value by using the SNMP Set operation. • By default, the Alerts goes to local syslog. So, this will enable Alerts to be sent as SNMP Traps as well. |
| Release | Release 8.0(1) |
| Associated CDETS # | None |