

Administration: CLI command utils dbreplication status all does not include Finesse tables

Problem Summary	The CLI command utils dbreplication status all does not include the Finesse tables in the results.
Error Message	N/A
Possible Cause	The script behind this CLI command checks the replication status of only the tables listed as part of the ccmdbtemplate.
Recommended Action	<ol style="list-style-type: none"> 1. Log in as root and run the command cdr list repl to get the list of Finesse replicates. Note: Contact Cisco Technical Support for assistance with this step. 2. From the list, choose the replicate ending with the Finesse table for which you want to find the replication status. 3. Run the command utils db replication status with the complete replicate name as the argument. For example, to find the replication status for the wrapupreason table, run the command utils dbreplication status template_db_phx_config_g_blr_fin_95_141_ccm10_0_0_95000_422_3_9_wrapupreason.
Release	Release 9.1(1), Release 10.0(1), Release 10.5(1), Release 11.0(1)
Associated CDETS #	None