

**AAS - AAS cannot connect to SCCS**

<b>Problem Summary</b>	AAS cannot connect to SCCS
<b>Error Message</b>	None
<b>Possible Cause</b>	None.
<b>Recommended Action</b>	<p>Reinstall AAS and enter correct information.</p> <p>The recommended actions are:</p> <ul style="list-style-type: none"> <li>• Check for the site name in TAO Naming Viewer. This service can be run from D:\Nortel\TAO14\bin. The site name mentioned should be same as specified in the AAS registry AASSEISiteName.</li> <li>• Check for the namesrv.properties (used by naming service, located somewhere like D:\Nortel\vbtr51\properties or just search for that file). Check for the line naming service listening port.</li> <li>• The naming listener port should be same as in AAS registry AASSEINamingServicePort and SEI.properties file. SEI.properties file can be found at D:\Nortel\TAO14\properties.</li> <li>• Do not use the local IP address (127.0.0.1) as an AAS IP address.</li> <li>• Specify the site name in host file.</li> </ul>
<b>Release</b>	Release 7.5(1) and 8.0
<b>Associated CDETS #</b>	None.