

**Main page:** [Cisco Unified MeetingPlace, Release 7.0](#)

**Up one level:** [Reference Information](#)

To find this page, click **System Configuration > Cisco WebEx Configuration > Cisco WebEx Site and Server**.

**Note:** This page was called "WebEx Site and Server" in Release 7.0.1.

**Table: Field Reference: Cisco WebEx Site and Server Page**

Field	Description
Web conference scheduling	<p>Configures Cisco WebEx integration:</p> <ul style="list-style-type: none"> <li>• Unified MP schedule, Unified MP meeting -- Cisco WebEx integration is disabled.</li> <li>• Unified MP schedule, Cisco WebEx meeting -- Specifies Integration Option 1: Schedule and Attend Cisco WebEx Meetings from Cisco Unified MeetingPlace. See <a href="#">About Integration Option 1: Schedule and Attend Cisco WebEx Meetings from Cisco Unified MeetingPlace</a>.</li> <li>• Cisco WebEx schedule, Cisco WebEx meeting -- Specifies Integration Option 2: Schedule and Attend Cisco WebEx Meetings from Cisco WebEx. See <a href="#">About Integration Option 2: Schedule and Attend Cisco WebEx Meetings from Cisco WebEx</a>.</li> </ul> <p>The value of this field also determines which other fields appear on this page.</p> <p>Restriction: Changes to this field take effect only after you do the following:</p> <ol style="list-style-type: none"> <li>1. Click Save.</li> <li>2. Click the <a href="#">Restart Cisco WebEx Adapter</a> or <a href="#">Reset TSP Connection</a> button.</li> <li>3. Wait 10 minutes for the system to transfer the configuration to the Web Server.</li> <li>4. Restart the Cisco Unified MeetingPlace Web Conferencing service on the Web Server. See <a href="#">Restarting All Web Conferencing Services</a>.</li> </ol> <p><b>NOTE:</b> When you restart the Web Server, all manual changes made to the registry are lost.</p> <p>Default: Unified MP schedule, Unified MP meeting (which hides all other fields on the page)</p>
Web conference meeting template	Which Cisco WebEx meeting template options to offer meeting schedulers.

	<p>Restriction: This field appears only when you have configured the <a href="#">Web conference scheduling</a> field to schedule Cisco WebEx meetings from Cisco Unified MeetingPlace user interfaces.</p>
Cisco WebEx site ID	<p>Cisco WebEx site parameters provided by your Cisco WebEx administrator.</p> <p>The <a href="#">Cisco WebEx site name</a> identifies your organization and becomes part of the URL for your Cisco WebEx site.</p>
Cisco WebEx site name	
Cisco WebEx partner ID	
Cisco WebEx site administration password	<p>Password provided by your Cisco WebEx administrator for accessing the Cisco WebEx Site Administration. Cisco Unified MeetingPlace always uses the user ID of "admin" profile for Cisco WebEx integrations and this cannot be changed. Only the password can be modified and must be modified in both the Cisco Unified MeetingPlace "admin" profile and in the Cisco WebEx Site Administration "admin" host ID.</p> <p>Combined with your system administrator "admin" user ID <a href="#">User ID</a>, the system uses this password to automatically sign you in to the Cisco WebEx Site Administration when you click the <a href="#">Cisco WebEx Site Administration URL</a> in the Administration Center.</p> <p>If this password is not configured correctly, or if your <a href="#">User ID</a> was modified after logging in to the Cisco WebEx Site Administration even once, you will be prompted to enter a username and password when you click one of the Administration Center links for the <a href="#">Cisco WebEx Site Administration URL</a>.</p>
Cisco WebEx site version	<i>Display only.</i> Cisco WebEx release number.
Proxy configuration required	<p>Provided by your network administrator.</p> <p>Proxy servers are often used with firewalls and may be optional.</p>
Proxy server hostname	Requirement: If you modify these fields after the connection with Cisco WebEx is already established, then you must click the <a href="#">Restart Cisco WebEx Adapter</a> button.
Proxy server port	<b>Caution!</b> This button causes the system to drop all Cisco WebEx meetings that are in session.
Cisco WebEx adapter status	<i>Display only.</i> Whether or not the adapter process is running.
Reset TSP Connection	<p>Establishes or resets the telephony connection between Cisco Unified MeetingPlace and Cisco WebEx.</p> <p>Updates the TSP primary host and TSP secondary host configuration from the Cisco</p>

	<p>WebEx site and then restarts the adapter.</p> <p><b>Caution!</b> This button causes the system to drop all Cisco WebEx meetings that are in session.</p>
Restart Cisco WebEx Adapter	<p>Restarts the adapter using the existing configuration for the TSP primary host and TSP secondary host.</p> <p>Use this button only if requested by Cisco TAC, by your Cisco WebEx service administrator, or after you modify the following fields:</p> <ul style="list-style-type: none"><li>• <u>Web conference scheduling</u></li><li>• <u>Proxy configuration required</u></li><li>• <u>Proxy server hostname</u></li><li>• <u>Proxy server port</u></li></ul> <p><b>Caution!</b> This button causes the system to drop all Cisco WebEx meetings that are in session.</p>

**Related Topics**

- [Integrating Cisco Unified MeetingPlace with Cisco WebEx](#)