

Main page: [Cisco Unity Express -- REST PI Service Operations](#)

Previous page: [Cisco Unity Express -- Caller Call Flow REST PI Service Operation](#)

Next page: [Cisco Unity Express -- Subscriber Notification Profile REST PI Service Operation](#)

Search the Cisco Unity Express documentation on the DocWiki:

Loading


Contents

- [1 Greetings](#)
 - ◆ [1.1](#)
 - [Classes](#)
 - ◇ [1.1.1](#)
[GreetingStatus](#)
 - ◇ [1.1.2](#)
[GreetingType](#)
 - ◇ [1.1.3](#)
[RecordingType](#)
 - ◇ [1.1.4](#)
[Greeting](#)
 - ◇ [1.1.5](#)
[UserRecording](#)
 - ◆ [1.2](#)
[Resources](#)

Greetings

Classes

Figure 25: Greeting



GreetingStatus

| | |
|----------------------|--|
| Class Name | GreetingStatus (Enumeration Class) |
| Extends From | |
| Description | Enumeration of greeting status types |
| XML Namespace | http://greeting.model.voicemail.rest.aesop.cisco.com |
| Enum Values | DISABLED, ENABLED, ENABLED_UNTIL |

GreetingType

| | |
|----------------------|---|
| Class Name | GreetingType (Enumeration Class) |
| Extends From | |
| Description | Enumeration of greeting types |
| XML Namespace | http://greeting.model.voicemail.rest.aesop.cisco.com |
| Enum Values | STANDARD, ALTERNATE, MEETING, VACATION, EXTENDEDABSENCE, BUSY, CLOSED, INTERNAL |

RecordingType

| | |
|----------------------|--|
| Class Name | RecordingType (Enumeration Class) |
| Extends From | |
| Description | Enumeration of recording types for a greeting |
| XML Namespace | http://greeting.model.voicemail.rest.aesop.cisco.com |
| Enum Values | SYSTEM, USER, NONE |

Greeting

| | | | |
|----------------------|--|--|---|
| Class Name | Greeting | | |
| Extends From | ManagedBaseElement | | |
| Description | Class representing configurations related to a specified greeting type for a given mailbox | | |
| XML Namespace | http://greeting.model.voicemail.rest.aesop.cisco.com | | |
| Field Name | Type | Constraints | Comments |
| enableUntil | DateTime | Must be specified if greetingStatus is set to ENABLED_UNTIL . Value must be less than 365 days in the future. | Enable a greeting until the specified date and time. |
| greetingStatus | GreetingStatus | | Greeting status |
| greetingType | GreetingType | | Greeting type |
| recordingType | RecordingType | | Recording type for this greeting |
| userRecording | UserRecording | | Indicates if user recorded custom greeting is present |

UserRecording

| | |
|----------------------|--|
| Class Name | UserRecording |
| Extends From | ManagedBaseElement |
| Description | Class representing user recorded custom greeting for a specified greeting type for a given mailbox |
| XML Namespace | http://greeting.model.voicemail.rest.aesop.cisco.com |

Resources

| Resource URI | Operation | Input | Return Value |
|--|--|-------|--|
| /voicemail/mailboxes/{ownerid}/greetings | GET (retrieve greetings information for all greeting types) | | BaseElementList Containing list of Greeting objects |

Cisco_Unity_Express_--_Greetings_REST_API_Service_Operation

| | | | |
|---|--|-------------------------------|----------------|
| /voicemail/mailboxes/{ownerid}/greetings/{greetingtype} | GET (Read Greeting information for a given greeting type) | | Greeting |
| /voicemail/mailboxes/{ownerid}/greetings/{greetingtype} | PUT (Update greeting information) | Content-type: application/xml | Greeting |
| /voicemail/mailboxes/{ownerid}/greetings/{greetingtype}/reset | PUT (Reset information for a greeting type to system defaults) | | |
| /voicemail/mailboxes/{ownerid}/greetings/{greetingtype}/recording | PUT (Upload a custom recorded wav file as a greeting) | Content-type: audio/x-wav | Audio WAV file |
| /voicemail/mailboxes/{ownerid}/greetings/{greetingtype}/recording | DELETE (Delete any custom recording for greeting type) | | |