

Links to Other API pages: [Cisco Unity Connection APIs](#)

CUPI Guide Contents
API Overview
Index of All CUPI Documentation

Contents

- [1 Changing a User's PIN](#)
- [2 Changing a User's Password](#)
- [3 Setting the "User Cannot Change Password" Flag](#)

Changing a User's PIN

A user's PIN is the password that a user must enter over the phone to sign in to their mailbox, so that they can listen to or send new messages by phone. To change a user's PIN you need the object ID of the user. The following example changes the user's PIN to 635241.

```
PUT vmrest/users/<objectid>/credential/pin

<?xml version="1.0" encoding="UTF-8"?>
<Credential>
  <Credentials>635241</Credentials>
</Credential>
```

Changing a User's Password

A user's password is the web application password required to interact with web applications, such as the PCA or the Inbox applications. The following example changes the user's password to My1stPassword.

```
PUT vmrest/users/<objectid>/credential/password

<?xml version="1.0" encoding="UTF-8"?>
<Credential>
  <Credentials>My1stPassword</Credentials>
</Credential>
```

Setting the "User Cannot Change Password" Flag

To configure a PIN or password so that the user cannot change it, use the CantChange element.

Here is an example of changing a user's PIN such that the user cannot change it.

```
PUT vmrest/users/<objectid>/credential/pin

<?xml version="1.0" encoding="UTF-8"?>
```

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_Changing_Passwords_and_Password_Settings

```
<Credential>  
  <CantChange>true</CantChange>  
</Credential>
```

Here is an example of changing a user's password such that the user cannot change it.

```
PUT vmrest/users/<objectid>/credential/password
```

```
<?xml version="1.0" encoding="UTF-8"?>  
<Credential>  
  <CantChange>true</CantChange>  
</Credential>
```

Note that the only difference in these examples is the URI; they both use the same Credentials object.