

Links to Other API pages: [Cisco Unity Connection APIs](#)

CUPI Guide Contents
API Overview
Index of All CUPI Documentation

Contents

- [1 Phone Menu API](#)
 - ◆ [1.1 Listing Phone Menu Fields](#)
 - ◆ [1.2 Updating Phone menu fields](#)
 - ◆ [1.3 Updating Conversation fields](#)
 - ◆ [1.4 Explanation of Data Fields](#)

Phone Menu API

Listing Phone Menu Fields

All the parameters of Phone Menu are present at the URI:

```
GET https://<connection-server>/vmrest/users/<user-objectid>
```

The following is the response from the above *GET* request and the actual response will depend upon the information given by you:

```
<User>
<URI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1</URI>
<ObjectId>4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1</ObjectId>
<UseDefaultLanguage>>true</UseDefaultLanguage>
<Alias>undeliverablemessagesmailbox</Alias>
<DisplayName>Undeliverable Messages</DisplayName>
<TimeZone>190</TimeZone>
<CreationTime>2013-03-05T10:54:38Z</CreationTime>
<IsTemplate>>false</IsTemplate>
<CosObjectId>610c9c71-32be-4465-b61a-523f24a9d828</CosObjectId>
<CosURI>/vmrest/coses/610c9c71-32be-4465-b61a-523f24a9d828</CosURI>
<Language>1033</Language>
<LocationObjectId>42a9ab40-490d-4819-9bfb-8ddce4f430ff</LocationObjectId>
<LocationURI>/vmrest/locations/connectionlocations/42a9ab40-490d-4819-9bfb-8ddce4f430ff</LocationURI>
<AddressMode>0</AddressMode>
<ClockMode>0</ClockMode>
<ConversationTui>SubMenu</ConversationTui>
<GreetByName>>true</GreetByName>
<ListInDirectory>>false</ListInDirectory>
<IsVmEnrolled>>true</IsVmEnrolled>
<SayCopiedNames>>true</SayCopiedNames>
<SayDistributionList>>true</SayDistributionList>
<SayMsgNumber>>true</SayMsgNumber>
<SaySender>>true</SaySender>
<SayTimestampAfter>>true</SayTimestampAfter>
```

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

```
<SayTimestampBefore>>false</SayTimestampBefore>
<SayTotalNew>>false</SayTotalNew>
<SayTotalNewEmail>>false</SayTotalNewEmail>
<SayTotalNewFax>>false</SayTotalNewFax>
<SayTotalNewVoice>>true</SayTotalNewVoice>
<SayTotalReceipts>>false</SayTotalReceipts>
<SayTotalSaved>>true</SayTotalSaved>
<Speed>100</Speed>
<MediaSwitchObjectId>ec1e2636-fc14-44fc-8cda-d6c1a3d61150</MediaSwitchObjectId>
<PhoneSystemURI>/vmrest/phonesystems/ec1e2636-fc14-44fc-8cda-d6c1a3d61150</PhoneSystemURI>
<Undeletable>>true</Undeletable>
<UseBriefPrompts>>false</UseBriefPrompts>
<Volume>50</Volume>
<EnAltGreetDontRingPhone>>false</EnAltGreetDontRingPhone>
<EnAltGreetPreventSkip>>false</EnAltGreetPreventSkip>
<EnAltGreetPreventMsg>>false</EnAltGreetPreventMsg>
<EncryptPrivateMessages>>false</EncryptPrivateMessages>
<DeletedMessageSortOrder>2</DeletedMessageSortOrder>
<SayAltGreetWarning>>false</SayAltGreetWarning>
<SaySenderExtension>>false</SaySenderExtension>
<SayAni>>false</SayAni>
<CallAnswerTimeout>4</CallAnswerTimeout>
<CallHandlerObjectId>13a3c5fc-f706-4bd0-aeeb-32dad2c4a29b</CallHandlerObjectId>
<CallhandlerURI>/vmrest/handlers/callhandlers/13a3c5fc-f706-4bd0-aeeb-32dad2c4a29b</CallhandlerURI>
<MessageTypeMenu>>false</MessageTypeMenu>
<NewMessageSortOrder>1</NewMessageSortOrder>
<SavedMessageSortOrder>2</SavedMessageSortOrder>
<MessageLocatorSortOrder>1</MessageLocatorSortOrder>
<NewMessageStackOrder>1234567</NewMessageStackOrder>
<SavedMessageStackOrder>1234567</SavedMessageStackOrder>
<EnablePersonalRules>>true</EnablePersonalRules>
<RecordUnknownCallerName>>true</RecordUnknownCallerName>
<RingPrimaryPhoneFirst>>false</RingPrimaryPhoneFirst>
<ExitAction>2</ExitAction>
<ExitTargetConversation>PHGreeting</ExitTargetConversation>
<PromptSpeed>100</PromptSpeed>
<ExitTargetHandlerObjectId>939d4d12-cec8-4fee-ae47-fbf0cf20c33e</ExitTargetHandlerObjectId>
<RepeatMenu>1</RepeatMenu>
<FirstDigitTimeout>5000</FirstDigitTimeout>
<InterdigitDelay>3000</InterdigitDelay>
<PromptVolume>50</PromptVolume>
<ExitCallActionObjectId>d6507973-3041-4798-ac83-c6c691cb9187</ExitCallActionObjectId>
<AddressAfterRecord>>false</AddressAfterRecord>
<DtmfAccessId>99999</DtmfAccessId>
<ConfirmDeleteMessage>>false</ConfirmDeleteMessage>
<ConfirmDeleteDeletedMessage>>false</ConfirmDeleteDeletedMessage>
<ConfirmDeleteMultipleMessages>>true</ConfirmDeleteMultipleMessages>
<IsClockMode24Hour>>false</IsClockMode24Hour>
<SynchScheduleObjectId>821f40e6-3a97-412c-ae7f-6c7ade9a754b</SynchScheduleObjectId>
<SynchScheduleURI>/vmrest/schedules/821f40e6-3a97-412c-ae7f-6c7ade9a754b</SynchScheduleURI>
<RouteNDRToSender>>true</RouteNDRToSender>
<IsSetForVmEnrollment>>true</IsSetForVmEnrollment>
<VoiceNameRequired>>false</VoiceNameRequired>
<SendBroadcastMsg>>false</SendBroadcastMsg>
<UpdateBroadcastMsg>>false</UpdateBroadcastMsg>
<ConversationVui>VuiStart</ConversationVui>
<ConversationName>SubMenu</ConversationName>
<SpeechCompleteTimeout>0</SpeechCompleteTimeout>
<SpeechIncompleteTimeout>750</SpeechIncompleteTimeout>
<UseVui>>false</UseVui>
<SkipPasswordForKnownDevice>>false</SkipPasswordForKnownDevice>
<JumpToMessagesOnLogin>>false</JumpToMessagesOnLogin>
<UseDefaultTimeZone>>true</UseDefaultTimeZone>
<EnableMessageLocator>>false</EnableMessageLocator>
```

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

```
<AssistantRowsPerPage>5</AssistantRowsPerPage>
<InboxMessagesPerPage>20</InboxMessagesPerPage>
<InboxAutoRefresh>15</InboxAutoRefresh>
<InboxAutoResolveMessageRecipients>true</InboxAutoResolveMessageRecipients>
<PcaAddressBookRowsPerPage>5</PcaAddressBookRowsPerPage>
<ReadOnly>>false</ReadOnly>
<EnableTts>true</EnableTts>
<SmtpAddress>undeliverablemessagesmailbox@ucbu-aricent-vm463.cisco.com</SmtpAddress>
<ConfirmationConfidenceThreshold>60</ConfirmationConfidenceThreshold>
<AnnounceUpcomingMeetings>60</AnnounceUpcomingMeetings>
<SpeechConfidenceThreshold>40</SpeechConfidenceThreshold>
<SpeechSpeedVsAccuracy>50</SpeechSpeedVsAccuracy>
<SpeechSensitivity>50</SpeechSensitivity>
<EnableVisualMessageLocator>>false</EnableVisualMessageLocator>
<ContinuousAddMode>>false</ContinuousAddMode>
<NameConfirmation>>false</NameConfirmation>
<CommandDigitTimeout>1500</CommandDigitTimeout>
<SaveMessageOnHangup>>false</SaveMessageOnHangup>
<SendMessageOnHangup>1</SendMessageOnHangup>
<SkipForwardTime>5000</SkipForwardTime>
<SkipReverseTime>5000</SkipReverseTime>
<UseShortPollForCache>>false</UseShortPollForCache>
<SearchByExtensionSearchSpaceObjectId>877942bf-6600-4b7a-809d-159199cfc2ec</SearchByExtensionSearchSpaceObjectId>
<SearchByExtensionSearchSpaceURI>/vmrest/searchspaces/877942bf-6600-4b7a-809d-159199cfc2ec</SearchByExtensionSearchSpaceURI>
<SearchByNameSearchSpaceObjectId>877942bf-6600-4b7a-809d-159199cfc2ec</SearchByNameSearchSpaceObjectId>
<SearchByNameSearchSpaceURI>/vmrest/searchspaces/877942bf-6600-4b7a-809d-159199cfc2ec</SearchByNameSearchSpaceURI>
<PartitionObjectId>da2114bf-cde7-43d8-9709-cd3895a9d41b</PartitionObjectId>
<PartitionURI>/vmrest/partitions/da2114bf-cde7-43d8-9709-cd3895a9d41b</PartitionURI>
<UseDynamicNameSearchWeight>>false</UseDynamicNameSearchWeight>
<LdapType>0</LdapType>
<CreateSmtpProxyFromCorp>>false</CreateSmtpProxyFromCorp>
<MwisURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/mwis</MwisURI>
<NotificationDevicesURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/notificationdevices</NotificationDevicesURI>
<MessageHandlersURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/messagehandlers</MessageHandlersURI>
<ExternalServiceAccountsURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/externalserviceaccounts</ExternalServiceAccountsURI>
<AlternateExtensionsURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/alternateextensions</AlternateExtensionsURI>
<PrivateListsURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/privatelists</PrivateListsURI>
<UserWebPasswordURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/credential/password</UserWebPasswordURI>
<UserVoicePinURI>/vmrest/users/4d5df6e3-a036-4f16-8f1e-d48e7e9b73c1/credential/pin</UserVoicePinURI>
<SmtpProxyAddressesURI>/vmrest/smtpproxyaddresses?query=(ObjectGlobalUserId%20is%204d5df6e3-a036-4f16-8f1e-d48e7e9b73c1)
</SmtpProxyAddressesURI>
<AlternateNamesURI>/vmrest/alternatenames?query=(GlobalUserId%20is%204d5df6e3-a036-4f16-8f1e-d48e7e9b73c1)
</User>
```

Response Code: 200

Updating Phone menu fields

To update the attributes of Phone Menu, the following steps can be followed:

PUT <https://<connection-server>/vmrest/users/<user-objectid>>

```
<User>
  <UseBriefPrompts>true</UseBriefPrompts>
  <PromptVolume>100</PromptVolume>
  <PromptSpeed>100</PromptSpeed>
  <IsClockMode24Hour>>false</IsClockMode24Hour>
  <ConversationTui>SubMenu</ConversationTui>
  <MessageLocatorSortOrder>1</MessageLocatorSortOrder>
  <JumpToMessagesOnLogin>>false</JumpToMessagesOnLogin>
</User>
```

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

The following is the response from the above *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

Updating Conversation fields

Example 1: Edit call actions

```
<User>
  <ExitAction>1</ExitAction>
</User>
```

The following is the response from the *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

Example 2: Edit call handler

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>PHTransfer</ExitTargetConversation>
  <ExitTargetHandlerObjectId>c1fc1029-55f4-40dc-a553-40b75664ed8a</ExitTargetHandlerObjectId>
</User>
```

The following URI can be used to view call handler template object ID:

GET https://<connection-server>/vmrest/handlers/callhandlers

The following is the response from the *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

Example 3: Interview handler

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>PHInterview</ExitTargetConversation>
  <ExitTargetHandlerObjectId>c1fc1029-55f4-40dc-a553-40b75664ed8a</ExitTargetHandlerObjectId>
</User>
```

The following is an example of the GET request that shows the interview handler template object ID:

GET https://<connection-server>/vmrest/handlers/interviewhandlers

The following is the response from the *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

Example 4: Directory handler

The following is an example of the GET request that shows the directory handler template object ID:

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

GET https://<connection-server>/vmrest/handlers/directoryhandlers

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>AD</ExitTargetConversation>
  <ExitTargetHandlerObjectId>c1fc1029-55f4-40dc-a553-40b75664ed8a</ExitTargetHandlerObjectId>
</User>
```

The following is the response from the *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

Example 5: Conversation

Request Body: for broadcast message administrator

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>BroadcastMessageAdministrator</ExitTargetConversation>
</UserTemplate>
```

The following is the response from the *PUT* request for broadcast message administrator and the actual response will depend upon the information given by you:

Response Code: 204

Request Body: for caller system transfer

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>SystemTransfer</ExitTargetConversation>
</User>
```

The following is the response from the *PUT* request for caller system transfer and the actual response will depend upon the information given by you:

Response Code: 204

Request Body: for greeting administrator

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>GreetingAdministrator</ExitTargetConversation>
</User>
```

The following is the response from the *PUT* request for greeting administrator and the actual response will depend upon the information given by you:

Response Code: 204

Request Body: for sign in

```
<UserTemplate>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>SubSignIn</ExitTargetConversation>
</UserTemplate>
```

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

The following is the response from the *PUT* request for sign in and the actual response will depend upon the information given by you:

Response Code: 204

Request Body: for user system transfer

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>SubSysTransfer</ExitTargetConversation>
</User>
```

The following is the response from the *PUT* request for user system transfer and the actual response will depend upon the information given by you:

Response Code: 204

Example 6: Users with Mailbox

```
<User>
  <ExitAction>2</ExitAction>
  <ExitTargetConversation>PHTransfer</ExitTargetConversation>
  <ExitTargetHandlerObjectId>71cb381b-fd16-4ba8-8a1d-e71684e57b0e</ExitTargetHandlerObjectId>
</User>
```

The following is the response from the *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

JSON Example To set exit action, do the following:

```
PUT https://<connection-server>/vmrest/users/<userobjectid>
Accept: application/json
Content-type: application/json
Connection: keep-alive
```

```
{
  "ExitAction": "2",
  "ExitTargetConversation": "SubSysTransfer"
}
```

The following is the response from the *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

Explanation of Data Fields

Field Name	Data Type	Operation	Description
UseBriefPrompts	Boolean	Read/Write	A flag indicating whether the subscriber hears brief or full phone menus when accessing Cisco Unity Connection over the phone.

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

			<p>Possible values:</p> <ul style="list-style-type: none"> • true: Brief • false: Full
PromptVolume	Integer	Read/Write	<p>The volume level for playback of system prompts. The range can vary from 0 to 100.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • 25: Low • 50: Medium • 100: High <p>Default Value: 50</p>
PromptSpeed	Integer	Read/Write	<p>The audio speed Cisco Unity Connection uses to play back prompts to the subscriber.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • 50: Slow • 100: Normal • 150: Fast • 200: Fastest <p>Default Value: 100</p>
IsClockMode24Hour	Boolean	Read/Write	<p>The time format used for the message timestamps that the subscriber hears when they listen to their messages over the phone.</p> <p>Possible values: ? true: 24-Hour Clock (00:00 - 23:59) ? false: 12-Hour Clock (12:00 AM - 11:59 PM) EnableMessageLocator Boolean Read/Write A flag indicating whether the message locator feature is enabled for the subscriber. Possible Values: ? false: Message locator feature is disabled for subscriber ? true: Message locator feature is enabled for subscriber Default Value: false RepeatMenu Integer Read/Write The number of times to repeat a menu in touchtone conversation. The range can vary from 0 to 250. Default value: 1 ConversationTui String Read/Write The name of the conversation the subscriber uses to set up, send, and retrieve messages. Possible values:</p> <ul style="list-style-type: none"> • SubMenu: Classic Conversation • SubMenu_Alternate_Custom: Custom keypad mapping1 • SubMenu_Alternate_Custom1: Custom keypad mapping1

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

			<ul style="list-style-type: none"> • SubMenu_AlternateN: Alternate Keypad Mapping(N) • SubMenu_AlternateS: Alternate Keypad Mapping(S) • SubMenu_AlternateX: Alternate Keypad Mapping (X) • SubMenuOpt1: Optional conversation1 • SubMenu_AlternateI: Standard Conversation
MessageLocatorSortOrder	Integer	Read/Write	<p>The order in which system will sort messages when the "Message Locator" feature is enabled.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • 1: Last In, First Out • 2: First In, First Out <p>Default Value: 1</p>
FirstDigitTimeout	Integer	Read/Write	<p>The amount of time to wait (in milliseconds) for first digit when collecting touchtone. The range can vary from 500 to 10000.</p> <p>Default value: 5000</p>
InterdigitDelay	Integer	Read/Write	<p>The amount of time to wait (in milliseconds) for input between touch tones when collecting digits in touchtone conversation. The range can vary from 1000 to 10000.</p> <p>Default Value: 3000</p>
CommandDigitTimeout	Integer	Read/Write	<p>The amount of time (in milliseconds) between digits on a multiple digit menu command entry (i.e. different than the inter digit timeout that is used for strings of digits such as extensions and transfer strings). The range can vary from 250 to 5000.</p> <p>Default value: 1500</p>
GreetByName	Boolean	Read/Write	<p>A flag indicating whether the subscriber hears his/her name when they log into their mailbox over the phone.</p> <p>Possible Values:</p> <ul style="list-style-type: none"> • false: Do not play the name. • true: Play the recorded voice name. <p>Default Value: true</p>
SayAltGreetWarning	Boolean	Read/Write	<p>A flag indicating whether Cisco Unity</p>

Cisco_Unity_Connection_Provisioning_Interface_(CUPI)_API_--_User_Phone_Menu_API

			<p>Connection notifies the subscriber when they login via the phone (plays conversation) or CPCA (displays a warning banner) if their alternate greeting is turned on.</p> <ul style="list-style-type: none"> • true- Notify the subscriber when they login if their alternate greeting is turned on • false: Do not notify the subscriber that their alternate greeting is turned on <p>Default Value: false</p>
JumpToMessagesOnLogin	Boolean	Read/Write	<p>A flag indicating whether the subscriber conversation jumps directly to the first message in the message stack after subscriber sign-in.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • false: Subscriber conversation does not jump directly to first message in the message stack after subscriber sign-in. • true: Subscriber conversation jumps directly to the first message in the message stack after subscriber sign-in. <p>Default Value: true</p>
ExitCallActionObjectId	String(36)	Read Only	<p>The unique identifier of the CallAction object that is taken when a caller exits the subscriber conversation by pressing the * key or timing out.</p>
ExitAction	Integer	Read/Write	<p>The type of call action to take, e.g., hang-up, goto another object, etc.</p> <p>Possible values: 0-8 Default Value: 0</p>
ExitTargetConversation	String(64)	Read/Write	<p>The name of the conversation to which the caller is routed.</p>
ExitTargetHandlerObjectId	String(36)	Read Only	<p>The unique identifier of the specific object to send along to the target conversation.</p>

NOTE: PromptVolume and PromptSpeed parameters must be of the same range given in the table.