

**Main page:** [Cisco Unified MeetingPlace, Release 7.0](#)

**Up one level:** [Reference Information](#)

Use this page when configuring your Microsoft Exchange Servers to send Exchange calendar notifications. Changes to this page impact Cisco Unified MeetingPlace users who have **E-Mail Type** set to **Exchange**.

To find this page, click **System Configuration > E-Mail Notifications > Exchange Server Configuration**.

**Note:** This page was introduced in Cisco Unified MeetingPlace Release 7.0.2 (MR1).

**Table: Field Reference: Exchange Server Configuration Page**

Field	Description
<b>Exchange Server</b>	
Hostname	<p>Hostname or IP address of the Microsoft Exchange Server.</p> <p><b>Note:</b> This field is supported for Release 7.0.2 (MR1) only.</p>
Hostname (SMTP)	<p>Hostname or IP address of the Microsoft Exchange Server running the SMTP service. This service is required for sending calendar notifications.</p> <p><b>Notes:</b></p> <ul style="list-style-type: none"> <li>• This field is required.</li> <li>• Supported for Release 7.0.3 (MR2) only.</li> </ul>
Hostname (WebDAV/EWS)	<p>Hostname or IP address of the Microsoft Exchange Server running the WebDAV/EWS service.</p> <p><b>Notes:</b></p> <ul style="list-style-type: none"> <li>• This field is optional. If your Exchange server runs both the email transmission and WebDAV/EWS extension services, leave this field blank. The system will automatically populate it with the information you provided for Hostname (SMTP).</li> <li>• Supported for Release 7.0.3 (MR2) only.</li> </ul>
Language	<p>Used to support localized Exchange servers.</p> <p>Default: en_US.</p>
TLS enabled	<p>If the Microsoft Exchange Server is configured to use TLS (Transport Layer Security) encryption, then set this to true.</p> <p>Default: false</p>
<b>MeetingPlace Mailbox Account</b>	

Windows domain	Microsoft Windows domain. Obtain this value from your Microsoft Exchange Server administrator.
Username	Username for the Cisco Unified MeetingPlace-dedicated email account on the Microsoft Exchange Server.  Example: MeetingPlace
Password Password confirm	Password for the Cisco Unified MeetingPlace-dedicated email account on the Microsoft Exchange Server.
E-mail address	Email address of the Cisco Unified MeetingPlace-dedicated email account on the Microsoft Exchange Server.  Example: MeetingPlace@example.com
Mailbox maintenance interval (days)	How often the Microsoft Exchange Server cleans up the mailbox for the Cisco Unified MeetingPlace-dedicated email account on the Microsoft Exchange Server.  A value of 0 disables this purge.  After you click <b>Save</b> on the <a href="#">Exchange Server Configuration Page</a> , the first purge occurs the following Sunday at 12:00 a.m. (local server time).  Default: 7
Mailbox maintenance cutover (days)	Number of days that notifications are stored in the mailbox for the Cisco Unified MeetingPlace-dedicated email account on the Microsoft Exchange Server.  Default: 14
Test	Use this button to verify the connection between Cisco Unified MeetingPlace and the Microsoft Exchange Server.

**Related Topics**

- [Enabling Microsoft Outlook Calendar Notifications for Meetings Scheduled from the Cisco Unified MeetingPlace End-User Web Interface](#)