

**Main page:** [Cisco Unified MeetingPlace, Release 7.1](#)

**Navigation:** [Integration](#) > [Integrating with Jabber](#)

## Contents

- [1 Stopping the cisco Component](#)
- [2 Removing the cisco Component](#)
- [3 Gathering Values for Uninstalling Jabber with Cisco Unified MeetingPlace](#)
- [4 Deleting the Jabber with Cisco Unified MeetingPlace Integration Files](#)
- [5 Removing the cisco Component Reference from the Jabber.Jig File](#)

## Stopping the cisco Component

### Procedure

1. Start the Jabber XCP Server Controller. See [Starting the Jabber XCP Server Controller](#).  
The system displays the Jabber XCP Controller System page.
2. Locate the cisco component in the Components section.
3. Click **Stop** in the Actions column.

## Removing the cisco Component

### Procedure

1. Stop the cisco component.
2. Click **Remove** in the Remove column.

## Gathering Values for Uninstalling Jabber with Cisco Unified MeetingPlace

Gather the following values, which are used in [Deleting the Jabber with Cisco Unified MeetingPlace Integration Files](#).

Parameter	Your Value
Installer source file directory	

<p>The directory that contains the installer source files.</p> <p>Example: /opt/jabber</p>
<p>JAR file directory</p> <p>The ./lib/cisco subdirectory of the directory that contains the installer source files.</p> <p>Example: /opt/jabber/lib/cisco</p>
<p>Cisco JIG configuration directory</p> <p>The ./schemas/jig/config/cisco subdirectory of the directory that contains the installer source files.</p> <p>Example: /opt/jabber/schemas/jig/config/cisco</p>
<p>Cisco XSD configuration directory</p> <p>The ./schemas/xsd/config/cisco subdirectory of the directory that contains the installer source files.</p> <p>Example: /opt/jabber/schemas/xsd/config/cisco</p>

## Deleting the Jabber with Cisco Unified MeetingPlace Integration Files

### Before You Begin

Gather the values in the [Gathering Values for Uninstalling Jabber with Cisco Unified MeetingPlace](#).

### Procedure

1. Log in to the Jabber XCP server as root.
2. Enter **rm -rf <JAR file directory>**.
3. Enter **rm -rf <Cisco JIG configuration directory>**.
4. Enter **rm -rf <Cisco XSD configuration directory>**.

## Removing the cisco Component Reference from the Jabber.Jig File

### Procedure

1. Log in to the Jabber XCP server as root.
2. Locate the jabber.jig file (for example, /opt/jabber/schemas/jig/config/jabber/jabber.jig).
3. Use a text editor to open the **jabber.jig** file.
4. Find and remove the following line of text: `<xi:include  
xi:href="{JABBER_HOME}/schemas/jig/config/cisco/cisco.jig" level="base"/>`
5. Save and close the **jabber.jig** file.