

**Main page:** [Cisco Unified MeetingPlace Express, Release 2.x](#)

**Previous page:** [Page References](#)

This page is used to export information about meeting participants who attended meetings during a specified range of dates. Topics in this section include:

- [Field Reference: Meeting Participants Report](#)
- [Output Fields of the Meeting Participants Report](#)

## Contents

- [1 Field Reference: Meeting Participants Report](#)
  - ◆ [1.1 Table: Fields on the Meeting Participants Report Page](#)
- [2 Output Fields of the Meeting Participants Report](#)
  - ◆ [2.1 Table: Output Fields of the Meeting Participants Report Page](#)

## Field Reference: Meeting Participants Report

**Table: Fields on the Meeting Participants Report Page**

Field	Description	Value
Destination	Destination of the exported information. For descriptions, restrictions, and recommendations for each option, see the <a href="#">How To Export Data</a> .	Screen/File/Printer Default: Screen
Include field header names	Whether or not to include the field header names in the exported file.	No/Yes Default: Yes
Start date	Earliest date for which you want to export meeting participant information.	Format: mm/dd/yyyy Default: yesterday's date
End date	Latest date for which you want to export meeting participant information.	Format: mm/dd/yyyy Default: today's date

## Output Fields of the Meeting Participants Report

**Table: Output Fields of the Meeting Participants Report Page**

<b>Field</b>	<b>Description</b>
PartID	A unique number that identifies this meeting participant.
ConfNum	See <a href="#">ConfNum</a> .
uid	The username used to log in to Cisco Unified MeetingPlace Express from a workstation (not from a phone).
nVSecInConf	The amount of time, in seconds, that this meeting participant spent in voice-only meetings.
nWFSecInConf	The amount of time, in seconds, that this meeting participant spent in full web meetings.
nSecsOutboundCalls	The total amount of time, in seconds, that this meeting participant spent on outgoing calls.
VNameHeader	Whether the participant's name is recorded.
nOutboundCalls	The number of outgoing calls initiated by this meeting participant.
nRetries	<i>Not supported.</i>
TNameHeader	First and last name of the meeting participant. For unprofiled users, this field is the name the user enters to join the meeting as a guest.
SpeakingAbility	The default speaking ability for this meeting participant. Can be either Listener or SpeakerPlus.
nVUIODsMade	<i>Not supported.</i>
nTimesQAsked	<i>Not supported.</i>
nTimesFGiven	<i>Not supported.</i>
UpdateTime	The date and time when the call was updated.  Note that this date and time has nothing to do with the values you entered in the Start date and End date fields on the Meeting Participant Information page.
nDCSecInConf	The total amount of time, in seconds, that this meeting participant was in the web meeting room.
nSecInMTGNotes	<i>Not supported.</i>