

**Main page:** [Cisco Unified MeetingPlace Express, Release 2.x](#)

**Previous page:** [Page References](#)

This page is used to export information about outgoing calls that were made from Cisco Unified MeetingPlace Express during a specified range of dates. Topics in this section include:

- [Field Reference: Outgoing Calls Information](#)
- [Output Fields of the Outgoing Calls Information Page](#)

## Contents

- [1 Field Reference: Outgoing Calls Information](#)
  - ◆ [1.1 Table: Fields on the Outgoing Calls Information Page](#)
- [2 Output Fields of the Outgoing Calls Information Page](#)
  - ◆ [2.1 Table: Output Fields of the Outgoing Calls Information Page](#)

## Field Reference: Outgoing Calls Information

**Table: Fields on the Outgoing Calls Information Page**

| Field                      | Description  | Value   |
|----------------------------|--|---|
| Destination                | Destination of the exported information. For descriptions, restrictions, and recommendations for each option, see the <a href="#">How To Export Data</a> . | Screen/File/Printer<br><br>Default: Screen          |
| Include field header names | Whether or not to include the field header names in the exported file.   | No/Yes<br><br>Default: Yes                          |
| Start date                 | Earliest date for which you want to export meeting dial-out information.   | Format: mm/dd/yyyy<br><br>Default: yesterday's date |
| End date                   | Latest date for which you want to export meeting dial-out information.   | Format: mm/dd/yyyy<br><br>Default: today's date     |

## Output Fields of the Outgoing Calls Information Page

**Table: Output Fields of the Outgoing Calls Information Page**

| <b>Field</b>    | <b>Description</b>  |
|-----------------|---|
| StartTimeOfCall | The date and time when the call started.  |
| uid             | See <a href="#">uid</a> .   |
| ConfNum         | See <a href="#">ConfNum</a> .   |
| nSeconds        | The duration of the outgoing call, in seconds.                                      |
| CalledDest      | The telephone number that was called.   |
| fBlastOutdial   | Whether this was a blast dial-out call.   |
| UpdateTime      | The date and time when the call was updated.  |
| partID          | Unique number that identifies the person who is being called from within a meeting. |