

This information describes how to complete a new installation of Cisco Unified MeetingPlace Web Conferencing. It does not describe upgrades.

**Note:** Before reviewing this information, read the [System Requirements](#). All installations of Release 6.1 require at least one Cisco MCS and a supported version of MCS OS 2003 software.

## Contents

- [1 Basic Installations](#)
- [2 Installations Allowing External Access](#)
- [3 Installations with Load Balancing](#)
- [4 Silently Installing the Cisco Unified Presenter Add-In on End-User Computers](#)
  - ◆ [4.1 Before You Begin](#)
  - ◆ [4.2 Restriction](#)
  - ◆ [4.3 Procedure](#)

## Basic Installations

- [Preinstallation Tasks: Web Conferencing](#)
- [Installation Tasks: Web Conferencing](#)
- [Postinstallation Tasks: Web Conferencing](#)

## Installations Allowing External Access

- [Installing Web Conferencing for a Segmented Meeting Access Configuration](#)

## Installations with Load Balancing

- [Installing Web Conferencing in a Load Balancing Configuration](#)

## Silently Installing the Cisco Unified Presenter Add-In on End-User Computers

This section describes how to use an automated distribution system, such as the Microsoft Systems Management Server (SMS), to remotely distribute and install the Cisco Unified Presenter Add-In.

## Cisco\_Unified\_MeetingPlace\_Release\_6.1\_--\_Installing\_Web\_Conferencing

By default, the system prompts end users to download and install the Cisco Unified Presenter Add-In the first time that they try to share content during a meeting. However, to simplify the process for end users, you can silently install the Cisco Unified Presenter Add-In onto their computers by using the following switches:

- **SILENT** - Does not display the wizard or the background window but does display the installation progress window.
- **VERYSILENT** - Does not display the wizard window, the background window, or the installation progress window.

### Before You Begin

Ensure that all end users have installed the Adobe Flash Player.

### Restriction

Cisco Systems does not provide technical support for automated distribution tools.

### Procedure

1. Download the Cisco Unified Presenter Add-In file called Setup.exe from the home page of the Cisco Unified MeetingPlace Web Server.
2. Upload the Cisco Unified Presenter Add-In file to your corporate distribution software site.
3. Run the executable by entering **setup.exe /silent**
4. To test the switch, do the following:
  1. Click **Start > Run**, and enter *<path\_to\_setup.exe> /silent*.
  2. Verify that no user prompts appear on the end user machine.