

Main page: [Cisco Unified MeetingPlace, Release 8.0](#)

Up one level: [Configuration](#)

- [Restrictions for Signing In to the Administration Center](#)
- [Signing In to the Administration Center for the First Time](#)

Contents

- [1 Restrictions for Signing In to the Administration Center](#)
 - ◆ [1.1 Related Topics](#)
- [2 Signing In to the Administration Center for the First Time](#)
 - ◆ [2.1 Procedure](#)
 - ◆ [2.2 Related Topics](#)
 - ◆ [2.3 What to Do Next](#)

Restrictions for Signing In to the Administration Center

- Only users of type [System administrator](#) or [Attendant](#) can sign in to the Administration Center.
- The preconfigured *admin* profile provides access only to the Administration Center on the Application Server. It does not provide system administrator access to the Web Administration on the Web Server.
- If you configured Directory Service on your system, only users who are authenticated locally by the Cisco Unified MeetingPlace database can access the Administration Center. Specifically, the [isLocalUser](#) setting in the user profile must be set to Yes. This prevents unauthorized access even if external directory passwords are compromised.

Related Topics

- [About User Types in the Administration Center Page References for Cisco Unified MeetingPlace \(A - C pages\)](#) module
- [Configuring Cisco Unified MeetingPlace Directory Service](#) module

Signing In to the Administration Center for the First Time

Procedure

1. Go to <http://application-server/admin/>.
2. Enter **admin** for user ID.
3. Enter the password for the [System administrator](#) that you created when you installed the Application Server.
The password is case-sensitive.
4. Select **Sign In**.

Related Topics

- [Recovering the User Password for the Preconfigured Admin Profile](#)
- [Admin Profile](#) in the [Configuring User Profiles and User Groups for Cisco Unified MeetingPlace](#) module
- [Accessibility Features in the Cisco Unified MeetingPlace Administration Center](#) module

What to Do Next

Proceed to [Changing the Passwords for the admin Profile](#) in the [Changing System Administrator Passwords for Cisco Unified MeetingPlace](#) module.