

Links to Other API pages: [Cisco Unity Connection APIs](#)

| |
|---|
| CUPI Guide Contents |
| API Overview |
| Index of All CUPI Documentation |

Contents

- [1 Unified Messaging Account API](#)
 - ◆ [1.1 Updating the Unified Messaging Account](#)
 - ◆ [1.2 Explanation of Data Fields](#)

Unified Messaging Account API

The following URI can be used to view the user template object ID:

```
GET https://<connection-server>/vmrestvmrest/usertemplates/<usertemplateobjectid>
```

From the above URI, get the unified messaging account:

```
GET https://<connection-server>/vmrestvmrest/usertemplates/<usertemplateobjectid>/templateexternalserviceaccounts
```

Updating the Unified Messaging Account

Request Body:

```
<TemplateExternalServiceAccount>  
  <EmailAddressUseCorp>true</EmailAddressUseCorp>  
  <EnableCalendarCapability>true</EnableCalendarCapability>  
  <EnableMailboxSynchCapability>true</EnableMailboxSynchCapability>  
  <EnableTtsOfEmailCapability>true</EnableTtsOfEmailCapability>  
</TemplateExternalServiceAccount>
```

The following is the response from the above *PUT* request and the actual response will depend upon the information given by you:

Response Code: 204

JSON Example

To view the unified messaging account, do the following:

Request URI:

```
GET https://<connection-server>/vmrest/usertemplates/<usertemplateobjectid>/templateexternalserviceaccounts  
Accept: application/json  
Content-type: application/json  
Connection: keep-alive
```

The following is the response from the above *GET* request and the actual response will depend upon the information given by you:

```
{
  "EmailAddressUseCorp": "true"
  "EnableCalendarCapability": "true"
  "EnableMailboxSynchCapability": "true"
  "EnablTtsOfEmailCapability": "true"
}
```

Response Code: 200

Explanation of Data Fields

| Device Name | Data Type | Operation | Comments |
|------------------------------|-----------|------------|--|
| EmailAddressUseCorp | Boolean | Read/Write | Use Corporate Email Address Default value: False |
| EnableTtsOfEmailCapability | Boolean | Read/Write | Access Exchange Email by Using Text to Speech (TTS) Default value: False |
| EnableCalendarCapability | Boolean | Read/Write | Access Exchange Calendar and Contacts Default value: False |
| EnableMailboxSynchCapability | Boolean | Read/Write | Synchronize Connection and Exchange Mailboxes (Single Inbox) Default value: False |