

**Main page:** [Cisco Unified MeetingPlace, Release 7.0](#)

**Up one level:** [Integrating with IBM Lotus Sametime Instant Messaging](#)

There are two ways that end users can access Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging: by the end user "pulling" it from the server or by having the server "push" it to the end user.

- [About Installing the Plug-In by Pulling it from the Server](#)
- [Installing the Plug-In by Pushing it to End Users](#)

## Contents

- [1 About Installing the Plug-In by Pulling it from the Server](#)
- [2 Installing the Plug-In by Pushing it to End Users](#)
  - ◆ [2.1 Configuring the Update Site in IBM Domino Administrator](#)
    - ◇ [2.1.1 Before You Begin](#)
    - ◇ [2.1.2 Procedure](#)
  - ◆ [2.2 Configuring the Update Site in the IBM Lotus Sametime Web Server](#)
    - ◇ [2.2.1 Procedure](#)

## About Installing the Plug-In by Pulling it from the Server

**Note:** We recommend using this method if installing Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging is optional for your end users. If installation is mandatory, we recommend that you push the plug-in to them as described in the following section.

End users can pull the plug-in from the server and install it themselves. To facilitate this, provide them with the following:

- The *Quick Start Guide for Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging for Cisco Unified MeetingPlace Release 6.x and 7.x* found here: [http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/meetingplace/7x/english/quickstart\\_guides/QSG\\_using\\_Sametime.html](http://www.cisco.com/en/US/docs/voice_ip_comm/meetingplace/7x/english/quickstart_guides/QSG_using_Sametime.html)  
This guide describes how to install, configure, and use Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging.
- The http path, discussed in the [Configuring the Update Site to Host Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging on your IBM Lotus Domino Server](#).

## Installing the Plug-In by Pushing it to End Users

- [Configuring the Update Site in IBM Domino Administrator](#)
- [Configuring the Update Site in the IBM Lotus Sametime Web Server](#)

### Configuring the Update Site in IBM Domino Administrator

#### Before You Begin

Log into IBM Domino Administrator.

#### Procedure

1. Select the tab for the domain that you are configuring.
2. Select the **Files** tab.
3. Open the Sametime configuration called stconfig.nsf by double-clicking on it.
4. Open the Community Client configuration by double-clicking on the date.
5. Enter the http path to the Update Site, as described in [Configuring the Update Site to Host Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging on your IBM Lotus Domino Server](#), into the URL for UIM Provisioning field.
6. Click **Close > Save**.

### Configuring the Update Site in the IBM Lotus Sametime Web Server

#### Procedure

1. Log in to your IBM Lotus Sametime server at <http://<your-sametime-server>/stcenter.nsf>.
2. Click **Administer the server**.
3. Click **Policies** in the left panel.
4. Click **Sametime Default Policy** in the right panel.
5. Scroll to the Instant Messaging section.
6. Enter the http path to the Update Site, as described in [Configuring the Update Site to Host Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging on your IBM Lotus Domino Server](#), into the Sametime update site URL field.
7. Click **OK**.
8. Restart your IBM Lotus Sametime server.