

Main page: [Cisco Unified MeetingPlace, Release 7.0](#)

Up one level: [Integrating with IBM Lotus Sametime Instant Messaging](#)

There are two ways that end users can access Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging: by the end user "pulling" it from the server or by having the server "push" it to the end user.

- [About Installing the Plug-In by Pulling it from the Server](#)
- [Installing the Plug-In by Pushing it to End Users](#)

Contents

- [1 About Installing the Plug-In by Pulling it from the Server](#)
- [2 Installing the Plug-In by Pushing it to End Users](#)
 - ◆ [2.1 Configuring the Update Site in IBM Domino Administrator](#)
 - ◇ [2.1.1 Before You Begin](#)
 - ◇ [2.1.2 Procedure](#)
 - ◆ [2.2 Configuring the Update Site in the IBM Lotus Sametime Web Server](#)
 - ◇ [2.2.1 Procedure](#)

About Installing the Plug-In by Pulling it from the Server

Note: We recommend using this method if installing Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging is optional for your end users. If installation is mandatory, we recommend that you push the plug-in to them as described in the following section.

End users can pull the plug-in from the server and install it themselves. To facilitate this, provide them with the following:

- The *Quick Start Guide for Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging for Cisco Unified MeetingPlace Release 6.x and 7.x* found here: http://www.cisco.com/en/US/docs/voice_ip_comm/meetingplace/7x/english/quickstart_guides/QSG_using_Sametime.html
This guide describes how to install, configure, and use Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging.
- The http path, discussed in the [Configuring the Update Site to Host Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging on your IBM Lotus Domino Server](#).

Installing the Plug-In by Pushing it to End Users

- [Configuring the Update Site in IBM Domino Administrator](#)
- [Configuring the Update Site in the IBM Lotus Sametime Web Server](#)

Configuring the Update Site in IBM Domino Administrator

Before You Begin

Log into IBM Domino Administrator.

Procedure

1. Select the tab for the domain that you are configuring.
2. Select the **Files** tab.
3. Open the Sametime configuration called stconfig.nsf by double-clicking on it.
4. Open the Community Client configuration by double-clicking on the date.
5. Enter the http path to the Update Site, as described in [Configuring the Update Site to Host Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging on your IBM Lotus Domino Server](#), into the URL for UIM Provisioning field.
6. Click **Close > Save**.

Configuring the Update Site in the IBM Lotus Sametime Web Server

Procedure

1. Log in to your IBM Lotus Sametime server at <http://<your-sametime-server>/stcenter.nsf>.
2. Click **Administer the server**.
3. Click **Policies** in the left panel.
4. Click **Sametime Default Policy** in the right panel.
5. Scroll to the Instant Messaging section.
6. Enter the http path to the Update Site, as described in [Configuring the Update Site to Host Cisco Unified MeetingPlace Click-to-Conference with IBM Lotus Sametime Instant Messaging on your IBM Lotus Domino Server](#), into the Sametime update site URL field.
7. Click **OK**.
8. Restart your IBM Lotus Sametime server.