

Main page: [Cisco Unified MeetingPlace Express, Release 2.x](#)

Previous page: [Page References](#)

This page is used to export user profile information from the Cisco Unified MeetingPlace Express database.

- [Field Reference: Profile Information](#)
- [Output Fields of the Profile Information Page-Used for Importing User Profiles](#)

Contents

- [1 Field Reference: Profile Information](#)
 - ◆ [1.1 Table: Fields on the Profile Information Page](#)
- [2 Output Fields of the Profile Information Page-Used for Importing User Profiles](#)
 - ◆ [2.1 Table: Output Fields of the Profile Information Page-Used to Import User Profiles](#)
 - ◆ [2.2 Related Topics](#)

Field Reference: Profile Information

Table: Fields on the Profile Information Page

Field	Description	Value
Destination	Destination of the exported information. For descriptions, restrictions, and recommendations for each option, see the How To Export Data .	Screen/File/Printer Default: Screen
Include field header names	Whether to include the field header names in the exported file.	No/Yes Default: Yes

Output Fields of the Profile Information Page-Used for Importing User Profiles

[Table: Output Fields of the Profile Information Page-Used to Import User Profiles](#) lists, in alphabetical order, the output fields that the system displays after exporting user profile information. It also includes field descriptions and values, which are useful when you use the exported output to create import files.

Table: Output Fields of the Profile Information Page-Used to Import User Profiles

Header Field	Description	Values
Required Header Fields for Importing User Profiles		
EncryptedProfilePWD or prfpwd	<p>Encrypted profile password. See Profile password.</p> <p>If you instead want to import an unencrypted profile password, modify the import file as follows:</p> <ol style="list-style-type: none"> 1. Leave the EncryptedProfilePWD field blank for the user. 2. Add the prfpwd header field for the unencrypted profile password. <p>Requirement: This field is required in the import file only when adding user profiles by import.</p> <p>Restrictions:</p> <ul style="list-style-type: none"> • The prfpwd field does not appear in exported output. The field is used only in import files. • If the user is authenticated by an external directory, you cannot modify this field. See the Methods for Adding New User Profiles. • This field cannot be modified in the preconfigured Guest profile. 	<p>EncryptedProfilePWD: password previously encrypted by Cisco Unified MeetingPlace Express</p> <p>prfpwd: 5 to 17 numeric characters</p>
EncryptedUserPWD or upwd	<p>Encrypted user password. See User password.</p> <p>If you instead want to import an unencrypted user password, modify the import file as follows:</p> <ol style="list-style-type: none"> 1. Leave the EncryptedUserPWD field blank for the user. 2. Add the upwd header field for the unencrypted password. <p>Requirement: This field is required in the import file only when adding user profiles by import.</p> <p>Restrictions:</p>	<p>EncryptedUserPWD: password previously encrypted by Cisco Unified MeetingPlace Express</p> <p>upwd: 5 to 17 alphanumeric characters</p>

Table: Output Fields of the Profile Information Page-Used to Import User Profiles

	<ul style="list-style-type: none"> • The <u>upwd</u> field does not appear in exported output. The field is used only in import files. • Unicode is not supported. • If the user is authenticated by an external directory, you cannot modify this field. See the <u>Methods for Adding New User Profiles</u>. 	
prfnum	See <u>Profile number</u> . Requirement: This field is required in the import file whether you are adding or deleting user profiles by import.	-
uid	See <u>User ID</u> . Requirement: This field is required in the import file whether you are adding or deleting user profiles by import.	-
Optional Header Fields for Importing User Profiles		
1stSearch		
2ndSearch	See <u>Search order for find me</u> .	-
3rdSearch		
abbprompts	<i>Not supported.</i>	-
allowguestoutdial	<i>Not supported.</i>	-
AllowInternetAccess	<i>Not supported.</i>	-
AllowVideoSched	<i>Not supported.</i>	-
altnotifprf	<i>Not supported.</i>	-
altphnum	<i>Not supported.</i>	-
anndpart	See <u>Departure announcement</u> .	-
annentry	See <u>Entry announcement</u> .	-
announceqarr	<i>Not supported.</i>	-
announceqdep	<i>Not supported.</i>	-
attndprf	See <u>Method of attending</u> .	-
autodistatts	<i>Not supported.</i>	-
autostrtrcrd	<i>Not supported.</i>	-
bcode	See <u>Billing code</u> .	-
canallowguestoutdial	<i>Not supported.</i>	-
CanChangeMtgID	<i>Not supported.</i>	-
canrecord	Whether the user can record meetings.	Yes/No/Group Default

Table: Output Fields of the Profile Information Page-Used to Import User Profiles

		Default: Group Default
chatlienttype	<i>Not supported.</i>	-
cnodial	See Can call out of meetings.	-
concurrentquestions	<i>Not supported.</i>	-
ctctuid	See User ID of delegate.	-
DayOfLastImmedMtg	(Read only) The date and time of the last immediate meeting that this user scheduled.	-
dflnotifprio	See Priority.	-
disablerollcall	<i>Not supported.</i>	-
emailaddr	See E-mail address.	-
EmailFormat	See E-mail format.	-
emailtype	See E-mail type.	-
fadvanceinfo	<i>Not supported.</i>	-
fallowdataconf	<i>Not supported.</i>	-
fallowguestview	See Show meetings in public listing.	-
fautoproenabled	See Skip pre-meeting option.	-
faxnum	<i>Not supported.</i>	-
faxlattblnum	<i>Not supported.</i>	-
fCanInviteRemoteServers	<i>Not supported.</i>	-
fchatsession	<i>Not supported.</i>	-
fEndMtgWarn	<i>Not supported.</i>	-
fismtgseminartype	<i>Not supported.</i>	-
fMtgExtendPrompts	<i>Not supported.</i>	-
fnm	See First name.	-
fqnadisable	<i>Not supported.</i>	-
fstartpeopleinwr	<i>Not supported.</i>	-
ftellpartpos	<i>Not supported.</i>	-
groupulallowed	<i>Not supported.</i>	-
grpname	See Group name. Restriction: If the import file contains the grpname header field, then all user profiles in the import file must have a valid entry for this field. For details, see the Requirements for Import Files.	-
grpnum	See Number. Restriction: If the import file contains the grpnum header field, then all user profiles in the import file must have a valid entry for this field. For details, see the Requirements for Import Files.	-
InternetEmailAddr	<i>Not supported.</i>	-
isLocalUser	Whether this user is authenticated locally.	Yes/No

Table: Output Fields of the Profile Information Page-Used to Import User Profiles

Cisco_Unified_MeetingPlace_Express,_Release_2.x_--_About_This_Page:_Profile_Information

	<ul style="list-style-type: none"> • If this field is set to Yes, this is a local user. • If this field is set to No, this user is authenticated by an external directory. 	Default: Yes
Inm	See <u>Last name</u> .	-
MaxImmedMtgsPerDay	<i>Not supported.</i>	-
MaximumMeeting Length	See <u>Maximum meeting length (minutes)</u> .	-
MaxVUIODsPerMtg	<i>Not supported.</i>	-
meetingcategory	<i>Not supported.</i>	-
mxattsprmtg	<i>Not supported.</i>	-
numdataparts	<i>Not supported.</i>	-
NumImmedMtgsOnThat Day	<i>Not supported.</i>	-
ODXLatTableNum	<i>Not supported.</i>	-
pgrnum	See <u>Pager #</u> .	-
pgrtype	See <u>Pager type</u> .	DID pager/non-DID pager/ gd Default: gd
phnum	See <u>Main phone #</u> .	-
playattlstfifo	<i>Not supported.</i>	-
preferredunit	<i>Not supported.</i>	-
privateulallowed	<i>Not supported.</i>	-
prmrynotifprf	<i>Not supported.</i>	-
profileflex1	<i>Not supported.</i>	-
profileflex2	<i>Not supported.</i>	-
profileflex3	<i>Not supported.</i>	-
profileflex4	<i>Not supported.</i>	-
profileflex5	<i>Not supported.</i>	-
profileflex6	<i>Not supported.</i>	-
profileflex7	<i>Not supported.</i>	-
publiculallowed	<i>Not supported.</i>	-
pwdonoutdial	See <u>Ask for profile password</u> .	-
pwdreq	See <u>Password required</u> .	-
qnanotify	<i>Not supported.</i>	-
rcvattswnotif	<i>Not supported.</i>	-
rcvnotifs	See <u>Enabled for receive</u> .	-
recordmtgs	<i>Not supported.</i>	-
ReserveVoiceLicenses	See <u>Reserve voice licenses when setting up meetings</u> .	-
RsvnlessCnfg	See <u>Use reservationless</u> .	-
RsvnlessCnfgGD	<i>Not supported.</i>	-
schedhomesiteonly	<i>Not supported.</i>	-
schedprefunitonly	<i>Not supported.</i>	-
screntry	<i>Not supported.</i>	-

Table: Output Fields of the Profile Information Page-Used to Import User Profiles

shrtmnus	<i>Not supported.</i>	-
site	<i>Not supported.</i>	-
sndinvlstwnotif	See Include participant list.	-
sndmtgpwdwnotif	See Include password.	-
sndnotifonmtgch	See Send if meeting changes.	-
sndnotifs	See Enabled for this meeting.	-
SSI_RollMapID	<i>Not supported.</i>	-
SSI_SiteID	<i>Not supported.</i>	-
SSI_SystemID	<i>Not supported.</i>	-
tzcode	<p>See Time zone.</p> <p>Recommendation: The integer value in the import file must match a value defined by Cisco Unified MeetingPlace Express. Therefore, either use an existing value from an export file, or use the group default value of "gd."</p> <p>Restriction: If the import file contains the tzcode header field, then all user profiles in the import file must have a valid entry for the field. For any invalid or blank tzcode values, the associated user profile is not imported, and an error is logged.</p>	gd/integer value
uactive	See User status.	-
updatetime	(Read Only) The date and time of the last change to a file or record associated with this user.	MM/DD/YYYY HH:MM
utype	See Type of user.	-
VideoEndPtBandwidth	<i>Not supported.</i>	-
VLanguage	See Language.	-
VName	<i>Not supported.</i>	-
VUPasswordLast Changed	(Read Only) Date and time the user password was last changed.	-
WFPASSWORDLast Changed	(Read Only) Date and time the profile password was last changed.	-
whocanattnd	See Who can attend.	-
whocanlstn	<i>Not supported.</i>	-

Related Topics

- [Examples of Import Files](#)
- [Importing Multiple User Profiles by Using the Import Process](#)
- [Deleting Multiple User Profiles by Using the Import Process](#)