

You can integrate Cisco Unity Connection with Cisco Unified MeetingPlace Express so that users can review upcoming meetings and join active meetings while on the phone or while using the Cisco Personal Communications Assistant (PCA). This is done by creating a Cisco Unified MeetingPlace Express API user that will enable read-only access by Cisco Unity Connection and by creating service accounts on Cisco Unity Connection.

Contents

- 1 Setting up the Configuration
 - ◆ 1.1 Adding an API User Account for Cisco Unity Connection
 - ◇ 1.1.1 Procedure
- 2 Scheduling a Meeting using Cisco Unified MeetingPlace Express and Cisco Unity Connection
 - ◆ 2.1 Procedure

Setting up the Configuration

1. In Cisco Unified MeetingPlace Express, add an API user called "Cisco Unity Connection." See the [Adding an API User Account for Cisco Unity Connection](#) section.
2. In Cisco Unity Connection, create a Cisco Unified MeetingPlace Express external service. See the "Creating an Integration with Cisco Unified MeetingPlace Express" procedure in the "Integrating with Cisco Unified MeetingPlace Express" chapter of the System Administration Guide for Cisco Unity Connection Release 2.x for step-by-step information on how to do this.
3. In Cisco Unity Connection, create service accounts for the individual users. See the "Configuring Users for the Cisco Unified MeetingPlace Express Integration" procedure in the "Integrating with Cisco Unified MeetingPlace Express" chapter of the System Administration Guide for Cisco Unity Connection Release 2.x for step-by-step information on how to do this.

Adding an API User Account for Cisco Unity Connection

Procedure

1. Log in to Cisco Unified MeetingPlace Express and click **Administration**.
2. Click **User Configuration > User Profile Management**.
3. Click **Add New**.
4. Enter values in the required fields. To work with Cisco Unity Connection:
 - ◆ Set the First name field to **Cisco Unity**.
 - ◆ Set the Last name field to **Connection**.
 - ◆ Set the Type of user field to **API User**.
 - ◆ Note the values you enter for the User ID, User password, and Profile number fields as these will be used again in Cisco Unity Connection.
5. Click **Save**.

Scheduling a Meeting using Cisco Unified MeetingPlace Express and Cisco Unity Connection

Procedure

1. Log in to Cisco Unified MeetingPlace Express as an end user.
2. Click **Schedule**.
3. Enter values in the required fields to schedule a new meeting for the current time and invite a user who has an account on Cisco Unity Connection.
4. Log in to the Cisco Unity Connection mailbox of the user that you invited to the Cisco Unified MeetingPlace Express meeting in [Step 3](#).
5. If the user account is configured for speech access, say **List Meetings**.
If the user account is not configured for speech access, press **6**, and then follow the prompts to list meetings.
6. When you hear the system announce the Cisco Unified MeetingPlace Express meeting that you just scheduled, either say **Join Meeting**, or press the applicable keys on the phone keypad to join the meeting.