

**Main page:** [Cisco Unified MeetingPlace Express, Release 2.x](#)

**Previous page:** [Installing Cisco Unified MeetingPlace Express](#)

## Before You Begin:

Perform the procedure here: [Configuring the Cisco Unified MeetingPlace Express Server](#)

## Procedure

1. The system displays the Cisco Application DVD page. Close the DVD-ROM drive that has the Cisco Unified MeetingPlace Express DVD in it.
2. Click **Install...**
3. Wait a few minutes while the installer loads.
4. The Cisco Unified MeetingPlace Express installer displays an introductory message. After reading it, click **Next**.
5. The Cisco Unified MeetingPlace Express installer displays the licensing agreement. After reading it, select **I accept the terms of the License Agreement** and click **Next**.
6. The Choose Server Type page appears. The default value of **Primary Server (Default)** is automatically selected. Click **Next**.
  - Note:** If you are installing a secondary server for use with a Segmented Meeting Access system, select **Secondary (External) Server**. Otherwise, do not select this option.
7. The Review Current eth0 Network Settings page appears and displays the eth0 values you entered in [Step 2](#) of the [Configuring the Cisco Unified MeetingPlace Express Server](#). Review these values to ensure they are correct.
  - ◆ If they are not correct, enter the correct values and click **Next**.
  - ◆ If they are correct, click **Next**.
  - Note:** Changing the values on this page overwrites the values you entered earlier.
8. The Review Current eth1 Network Settings page appears and displays the eth1 values you entered in [Step 2](#) of the [Configuring the Cisco Unified MeetingPlace Express Server](#). Review these values to ensure they are correct.
  - ◆ If they are not correct, enter the correct values and click **Next**.
  - ◆ If they are correct, click **Next**.
  - Note:** Changing the values on this page overwrites the values you entered earlier.
9. The Review Current DNS Network Settings page appears and displays the DNS values you entered in [Step 2](#) of the [Configuring the Cisco Unified MeetingPlace Express Server](#). Review these values to ensure they are correct.
  - ◆ If they are not correct, enter the correct values and click **Next**.
  - ◆ If they are correct, click **Next**.
  - Note:** Changing the values on this page overwrites the values you entered earlier.
10. The Review New Network Settings page appears and displays all the network values you entered in [Step 2](#) of the [Configuring the Cisco Unified MeetingPlace Express Server](#). Review these values to ensure they are correct. If they are correct, click **Next**.
  - ◆ If they are not correct, click **Previous** to go back to the previous pages and make changes.
  - ◆ If they are correct, click **Next**.
  - Note:** Changing the values on this page overwrites the values you entered earlier.
11. The Configure NIC Settings page appears.
  - ◆ If your system uses [Auto Negotiation](#), click **On**. The system automatically takes you to [Step 13](#).
  - ◆ If your system does not use [Auto Negotiation](#), click **Off** and proceed to [Step 12](#).
  - Note:** Changing the values on this page overwrites the values you entered earlier.

12. If your system does not use auto-negotiation, you must set the Speed (Full Duplex) and Duplex mode values. Select a speed and duplex mode for your system. Click **Next**.

**Note:** Changing the values on this page overwrites the values you entered earlier.

**Note:** Review these network setting values carefully. If you need to change them after the installation is complete, you must use the **net** command. See the Configuration and Maintenance Guide for Cisco Unified MeetingPlace Express Release 2.x for more information about using the **net** command.

13. The Cisco Unified MeetingPlace Express installer prompts you to create a Password for the user called *root*. The password must be at least eight characters and can contain any printable ASCII characters. The password is case-sensitive. Enter a password and then confirm the password. Click **Next**.
14. The Cisco Unified MeetingPlace Express installer prompts you to create a Password for the user called *mpxadmin*. The password must be at least eight characters and can contain any printable ASCII characters. The password is case-sensitive. Enter a password and then confirm the password. Click **Next**.
15. **For Release 2.1 only:** The Cisco Unified MeetingPlace Express installer prompts you to create a Password for the Administration Center user called *admin*. The password must be at least eight characters and can contain any printable ASCII characters. The password is case-sensitive. Enter a password and then confirm the password. Click **Next**.
16. Review the pre-installation summary. Values include the product name, install folder, and the amount of disk space required and available for the installation target. If all the values are correct, click **Install**.

The Cisco Unified MeetingPlace Express installer installs the Cisco Unified MeetingPlace Express application. This can take between seven and 25 minutes.

When the installation is complete, the Cisco Unified MeetingPlace Express installer displays the Install Complete page.

**Note:** If the Install Complete page displays a message stating that there were errors during the installation, uninstall the application, reboot the computer, and install everything again. If you still get errors after installing the operating system and application the second time, go to the log to see the error messages. The log is located at `MPX_<version number>_InstallLog.log`.

17. Click **Done** to finish the installation. The DVD-ROM drive ejects the DVD.

**Note:** Wait until the DVD-ROM drive ejects the DVD before removing it.

18. Remove the Cisco Unified MeetingPlace Express DVD from the DVD-ROM drive. If you did not make any changes to the network settings in [Step 7](#), [Step 8](#), or [Step 9](#), the Cisco Application DVD page appears.

**Note:** If you made changes to the network settings then your machine automatically restarts. When it comes back up, the system displays the Cisco Unified MeetingPlace Express operating system login page and the Cisco Unified MeetingPlace Express system is now completely installed. Proceed to [How to Test the Cisco Unified MeetingPlace Express Installation](#).

19. Click **Next**. The Finish Setup page appears.

20. Click **Finish**. The system displays the Cisco Unified MeetingPlace Express operating system login page.