

**Main page:** [Cisco Unified Presence, Release 7.x](#)

Using the following procedures, you can review the last 20 backup and restore jobs that have been performed.

## Contents

- [1 Previous Topic](#)
- [2 Viewing the Restore Status](#)
  - ◆ [2.1 Procedure](#)
  - ◆ [2.2 Related Topics](#)
- [3 Viewing the Backup History](#)
  - ◆ [3.1 Procedure](#)
  - ◆ [3.2 Related Topics](#)
- [4 Viewing the Restore History](#)
  - ◆ [4.1 Procedure](#)
  - ◆ [4.2 Related Topics](#)

**Previous Topic**

[How to Back Up Data in the Disaster Recovery System](#) OR [How to Restore Data in the Disaster Recovery System](#)

- [Viewing the Restore Status](#)
- [Viewing the Backup History](#)
- [Viewing the Restore History](#)

## Viewing the Restore Status

While the restore process is running, you can check the status of the current restore job.

### Procedure

1. Select **Navigation > Disaster Recovery System** from the menu in the upper, right corner of Cisco Unified Presence main window.
2. Click **Go**.
3. Enter the same Administrator username and password that you use for the Cisco Unified Operating System.
4. Select **Restore > Status**.

5. Click the log filename hyperlink to view the restore log file.
6. Click **Refresh** if required.

#### Related Topics

- [About BackUp and Restore Troubleshooting Operations](#)
- [Getting More Information](#)

## Viewing the Backup History

From the Backup History window, you can view the backups that you have performed, including filename, storage location, completion date, result, and features that are backed up.

#### Procedure

1. Select **Navigation > Disaster Recovery System** from the menu in the upper, right corner of Cisco Unified Presence main window.
2. Click **Go**.
3. Enter the same Administrator username and password that you use for the Cisco Unified Operating System.
4. Select **Backup > History** to view the last 20 backup jobs.
5. Click **Refresh** if required.

#### Related Topics

- [About BackUp and Restore Troubleshooting Operations](#)
- [Getting More Information](#)

## Viewing the Restore History

You can check the status of the current backup job and cancel the current backup job. In the Restore History window, you can view the restore operations that you have performed, including filename, storage location, completion date, result, and the features that were restored.

#### Procedure

1. Select **Navigation > Disaster Recovery System** from the menu in the upper, right corner of Cisco Unified Presence main window.
2. Click **Go**.

3. Enter the same Administrator username and password that you use for the Cisco Unified Operating System.
4. Select **Restore > History** to view the last 20 restore jobs.
5. Click **Refresh** if required.

#### **Related Topics**

- [About BackUp and Restore Troubleshooting Operations](#)
- [Getting More Information](#)