

**Links to Other API pages:** [Cisco Unity Connection APIs](#)

<b>CUPI Guide Contents</b>
<a href="#">API Overview</a>
<a href="#">Index of All CUPI Documentation</a>

## Contents

- [1 About Default Templates](#)
- [2 Listing Default Templates](#)
- [3 Modifying Default Templates](#)

## About Default Templates

This section contains information on how to list and modify default User Templates. Cisco Unity Connection comes with the following predefined user templates, which you can modify but not delete:

- Voice Mail User Template
- Administrator Template

For information on minimum software required with this API, see

[Cisco Unity Connection Provisioning Interface \(CUPI\) API -- Basic User Template Information#Minimum Software](#)

## Listing Default Templates

### Example 1

The following is an example of the GET request that lists the default User Templates:

```
https://<connection_server>/vmrest/userdefaulttemplates
```

The following is an example of the response from the above \*GET\* request and the actual response will depend upon the information given by you:

```
<DefaultUserTemplates total="2">
<DefaultUserTemplate>
  <URI>
    /vmrest/defaultusertemplates/48caecef-6f7a-47aa-91cb-019b761fce69
  </URI>
  <ObjectId>48caecef-6f7a-47aa-91cb-019b761fce69</ObjectId>
  <UseDefaultLanguage>true</UseDefaultLanguage>
  <UseDefaultTimeZone>true</UseDefaultTimeZone>
  <Alias>administratortemplate1</Alias>
  <City/>
  <State/>
  <Country>US</Country>
```

## Cisco\_Unity\_Connection\_Provisioning\_Interface\_(CUPI)\_API\_--\_Default\_User\_Template

```
<PostalCode/>
<Department/>
<Building/>
<Address/>
<DisplayName>Administrator Template</DisplayName>
<BillingId/>
<TimeZone>190</TimeZone>
<CreationTime>2012-07-09T07:27:43Z</CreationTime>
<Language>1033</Language>
<LocationObjectId>be27976c-6e6e-419f-853d-b3764881dfb0</LocationObjectId>
<LocationURI>
  /vmrest/locations/connectionlocations/be27976c-6e6e-419f-853d-b3764881dfb0
</LocationURI>
<DisplayNameRule>1</DisplayNameRule>
<DoesntExpire>>false</DoesntExpire>
<CantChange>>false</CantChange>
<RouteNDRToSender>>true</RouteNDRToSender>
<Undeletable>>true</Undeletable>
<ReadOnly>>false</ReadOnly>
<PartitionObjectId>c2ecf6c5-b3c2-45f4-99fc-e065056501d5</PartitionObjectId>
<PartitionURI>
  /vmrest/partitions/c2ecf6c5-b3c2-45f4-99fc-e065056501d5
</PartitionURI>
<LdapType>0</LdapType>
<CreateSmtProxyFromCorp>>false</CreateSmtProxyFromCorp>
<DefaultUserTemplateWebPasswordURI>
  /vmrest/usertemplates/48caecef-6f7a-47aa-91cb-019b761fce69/credential/password
</DefaultUserTemplateWebPasswordURI>
<DefaultUserTemplateVoicePinURI>
  /vmrest/usertemplates/48caecef-6f7a-47aa-91cb-019b761fce69/credential/pin
</DefaultUserTemplateVoicePinURI>
</DefaultUserTemplate>
<DefaultUserTemplate>
  <URI>
    /vmrest/defaultusertemplates/bc0eedd5-0483-4362-a091-5f89d27b7b3c
  </URI>
  <ObjectId>bc0eedd5-0483-4362-a091-5f89d27b7b3c</ObjectId>
  <UseDefaultLanguage>>true</UseDefaultLanguage>
  <UseDefaultTimeZone>>true</UseDefaultTimeZone>
  <Alias>voicemailusertemplate</Alias>
  <DisplayName>Voice Mail User Template</DisplayName>
  <TimeZone>190</TimeZone>
  <CreationTime>2012-07-09T07:27:44Z</CreationTime>
  <CosObjectId>305a9699-03a8-41d0-9215-0fcd32d600b0</CosObjectId>
  <CosURI>/vmrest/coses/305a9699-03a8-41d0-9215-0fcd32d600b0</CosURI>
  <Language>1033</Language>
  <LocationObjectId>be27976c-6e6e-419f-853d-b3764881dfb0</LocationObjectId>
  <LocationURI>
    /vmrest/locations/connectionlocations/be27976c-6e6e-419f-853d-b3764881dfb0
  </LocationURI>
  <DisplayNameRule>1</DisplayNameRule>
  <DoesntExpire>>false</DoesntExpire>
  <CantChange>>false</CantChange>
  <MailboxStoreObjectId>15dd71c8-2ba1-4efa-a34e-01613a0d2ef7</MailboxStoreObjectId>
  <RouteNDRToSender>>true</RouteNDRToSender>
  <Undeletable>>true</Undeletable>
  <ReadOnly>>false</ReadOnly>
  <PartitionObjectId>c2ecf6c5-b3c2-45f4-99fc-e065056501d5</PartitionObjectId>
  <PartitionURI>
    /vmrest/partitions/c2ecf6c5-b3c2-45f4-99fc-e065056501d5
  </PartitionURI>
  <LdapType>0</LdapType>
  <CreateSmtProxyFromCorp>>false</CreateSmtProxyFromCorp>
  <DefaultUserTemplateWebPasswordURI>
```

## Cisco\_Unity\_Connection\_Provisioning\_Interface\_(CUPI)\_API\_--\_Default\_User\_Template

```
/vmrest/usertemplates/bc0eedd5-0483-4362-a091-5f89d27b7b3c/credential/password
</DefaultUserTemplateWebPasswordURI>
<DefaultUserTemplateVoicePinURI>
/vmrest/usertemplates/bc0eedd5-0483-4362-a091-5f89d27b7b3c/credential/pin
</DefaultUserTemplateVoicePinURI>
</DefaultUserTemplate>
</DefaultUserTemplates>
```

Response code: 200

### Example 2

The following is an example of the GET request that lists a specified default User Templates:

```
https://<connection_server>/vmrest/userdefaulttemplates/<objectId>
```

The following is an example of the response from the above \*GET\* request and the actual response will depend upon the information given by you:

```
<DefaultUserTemplate>
<URI>
 /vmrest/defaultusertemplates/48caecef-6f7a-47aa-91cb-019b761fce69
</URI>
<ObjectId>48caecef-6f7a-47aa-91cb-019b761fce69</ObjectId>
<UseDefaultLanguage>true</UseDefaultLanguage>
<UseDefaultTimeZone>true</UseDefaultTimeZone>
<Alias>administratortemplate1</Alias>
<City/>
<State/>
<Country>US</Country>
<PostalCode/>
<Department/>
<Building/>
<Address/>
<DisplayName>Administrator Template</DisplayName>
<BillingId/>
<TimeZone>190</TimeZone>
<CreationTime>2012-07-09T07:27:43Z</CreationTime>
<Language>1033</Language>
<LocationObjectId>be27976c-6e6e-419f-853d-b3764881dfb0</LocationObjectId>
<LocationURI>
 /vmrest/locations/connectionlocations/be27976c-6e6e-419f-853d-b3764881dfb0
</LocationURI>
<DisplayNameRule>1</DisplayNameRule>
<DoesntExpire>>false</DoesntExpire>
<CantChange>>false</CantChange>
<RouteNDRToSender>true</RouteNDRToSender>
<Undeletable>true</Undeletable>
<ReadOnly>>false</ReadOnly>
<PartitionObjectId>c2ecf6c5-b3c2-45f4-99fc-e065056501d5</PartitionObjectId>
<PartitionURI>
 /vmrest/partitions/c2ecf6c5-b3c2-45f4-99fc-e065056501d5
</PartitionURI>
<LdapType>0</LdapType>
<CreateSmtProxyFromCorp>>false</CreateSmtProxyFromCorp>
<DefaultUserTemplateWebPasswordURI>
 /vmrest/usertemplates/48caecef-6f7a-47aa-91cb-019b761fce69/credential/password
</DefaultUserTemplateWebPasswordURI>
<DefaultUserTemplateVoicePinURI>
```

## Cisco\_Unity\_Connection\_Provisioning\_Interface\_(CUPI)\_API\_--\_Default\_User\_Template

```
/vmrest/usertemplates/48caecef-6f7a-47aa-91cb-019b761f6e69/credential/pin
</DefaultUserTemplateVoicePinURI>
</DefaultUserTemplate>
```

Response code: 200

## Modifying Default Templates

The following is an example of the PUT request that modifies the Default User Templates:

```
https://<connection_server>/vmrest/userdefaulttemplates/<objectId>
```

The actual response will depend upon the information given by you.

```
<DefaultUserTemplate>
  <City>San Jose</City>
  <State>CA</State>
  <Country>US</Country>
</DefaultUserTemplate>
```

Response code: 204