

**Main page:** [Cisco Unity Express -- REST PI Service Operations](#)

**Previous page:** [Cisco Unity Express -- License Information REST PI Service Operation](#)

**Next page:** [Cisco Unity Express -- SMTP Server REST PI Service Operation](#)

**Search the Cisco Unity Express documentation on the DocWiki:**

Loading

---


## Contents

- [1 NTP Server](#)
  - ◆ [1.1 Classes](#)
    - ◇ [1.1.1 NTPServer](#)
    - ◇ [1.1.2 NTPServerList](#)
  - ◆ [1.2 Resources](#)

## NTP Server

### Classes

**Figure 20: NTP Server**



## Cisco\_Unity\_Express\_--\_NTP\_Server\_REST\_PI\_Service\_Operation

### NTPServer

|                      |                                       |                    |   |
|----------------------|---------------------------------------|--------------------|---|
| <b>Class Name</b>    | NTPServer                             |                    |   |
| <b>Extends From</b>  | ManagedBaseElement                    |                    |   |
| <b>Description</b>   | Class representing an NTP server      |                    |   |
| <b>XML Namespace</b> | http://ntp.model.rest.aesop.cisco.com |                    |   |
| <b>Field Name</b>    | <b>Type</b>                           | <b>Constraints</b> | <b>Comments</b>                           |
| address              | String                                |                    | Host name or IP address of the NTP server |

### NTPServerList

|                      |  |                    |                           |
|----------------------|--|--------------------|---------------------------|
| <b>Class Name</b>    | NTPServerList                            |                    |                           |
| <b>Extends From</b>  | ManagedBaseElement                       |                    |                           |
| <b>Description</b>   | Class representing a list of NTP servers |                    |                           |
| <b>XML Namespace</b> | http://ntp.model.rest.aesop.cisco.com    |                    |                           |
| <b>Field Name</b>    | <b>Type</b>                              | <b>Constraints</b> | <b>Comments</b>           |
| ntpServer            | NTPServer (collection)                   |                    | List of NTPServer objects |

### Resources

| Resource URI                  | Operation                                 | Input         | Return Value  |
|-------------------------------|---|---------------|---------------|
| /system/ntp/servers           | GET (read list of NTP servers configured) |               | NTPServerList |
|                               | PUT (Update list of NTP servers)          | NTPServerList |               |
|                               | POST (Add an NTP server to the list)      | NTPServer     |               |
| /system/ntp/servers/{address} | GET (Read a NTP server )                  |               | NTPServer     |
|                               | DELETE (Remove NTP server )               |               |               |