

**Data Sources: Database connection failure**

<b>Problem Summary</b>	Test Connection fails for the data source
<b>Error Message</b>	Various
<b>Possible Cause</b>	<p>Possible causes include:</p> <ul style="list-style-type: none"> <li>* Invalid username or password</li> <li>* Invalid database name</li> <li>* Invalid DNS name or IP address of database server</li> <li>* Invalid Database port</li> <li>* Database port is blocked by Router/Firewall</li> <li>* MS SQL Server is not set to ?Mixed Authentication Mode?</li> <li>* Invalid Database Instance name (for Informix)</li> <li>* Invalid Charset</li> <li>* Loss of network connection or sluggish connection</li> <li>* Database user does not have the permission to access the required database</li> <li>* Database TCP/IP protocol and/or remote connection is not correctly configured.</li> <li>* Database service is not restarted after configuration changes</li> </ul>
<b>Recommended Action</b>	Consider the list of possible causes. Determine and prioritize which might be the cause in your situation. Resolve appropriately.
<b>Release</b>	Release 8.0(1)
<b>Associated CDETS #</b>	None