

[Cisco Unified MeetingPlace, Release 6.x](#) > [Web Conferencing](#) > [Configuring](#) > [Web Conferencing and SQL Server](#)

This section describes part of the process for relocating the Cisco Unified MeetingPlace Web Server (MPWEB) database to a dedicated Microsoft SQL Server instance.

For performance and management reasons, you can choose to relocate the Cisco Unified MeetingPlace Web Conferencing SQL database (MPWEB) to your own standalone instance of Microsoft SQL Server 2000 or 2005 (in backward compatibility mode). For requirements for the customer-provided Microsoft SQL Server, see *SQL Server Requirements?Remote (Off Box)* in [SQL Server Requirements](#).

To detach and attach the MPWEB SQL database, or relocate the database, do the following procedures in the order shown:

- [To Detach the Database](#)
- [To Attach the Database](#)
- [To Relocate the Database](#)

## Contents

- [1 To Detach the Database](#)
  - ◆ [1.1 Examples: Detaching the Database](#)
  - ◆ [1.2 Sample Output for Connecting to SQL Server](#)
  - ◆ [1.3 Sample Output for Accessing the MPWEB Database](#)
  - ◆ [1.4 Sample Output for Displaying a List of Database Files](#)
  - ◆ [1.5 Sample Output for Accessing the SQL Server Master Database](#)
  - ◆ [1.6 Sample Output for Detaching the MPWEB Database](#)
  - ◆ [1.7 Sample Output for Determining the Slave Database Name](#)
  - ◆ [1.8 Sample Output for Exiting osql](#)
- [2 To Attach the Database](#)
  - ◆ [2.1 Examples: Attaching the Database](#)
  - ◆ [2.2 Sample Output for Connecting to SQL Server](#)
  - ◆ [2.3 Sample Output for Checking if the MPWEB Database Exists](#)
  - ◆ [2.4 Sample Output for Checking the Physical Location of the SQL Server Master Database](#)
  - ◆ [2.5 Sample Output for Attaching the MPWEB Database](#)
  - ◆ [2.6 Sample Output for Exiting osql](#)
- [3 To Relocate the Database](#)

## To Detach the Database

You must detach the MPWEB database with the `sp_detach_db` command from a SQL Server release that is earlier or equal to the release of the SQL Server to which you want to import the database.

1. On the Cisco Unified MeetingPlace web server, log on as administrator.

2. Stop the Cisco MeetingPlace Web Conferencing service and wait for the Cisco MeetingPlace Web Conferencing services, IIS Admin service, and World Wide Web Publishing service to stop.
3. If the SQL Server hosting the MPWEB database runs on the Cisco Unified MeetingPlace web server, continue with [Step 4](#).
  - or
  - If the SQL Server hosting the MPWEB database runs on a separate (remote) Windows server, locate that Windows server and log on.
  - Note:** If you cannot log on to the separate (remote) Windows server, log on to any Windows based workstation or server on the network that has a valid installation of SQL Server Client tools, including the osql command, so that you can remotely connect to the SQL Server.
4. Access the command prompt. Choose **Start > Run** , then enter **cmd** .
5. Connect to SQL Server by using osql with the SA account and the appropriate password.
  - ◆ If the SQL Server runs locally, you can omit the **-S servername** option.
  - ◆ If you are not allowed to connect to this SQL Server as SA, connect by using an account that has enough privileges to backup a database.
6. Access the MPWEB database. Enter **use mpweb** , then enter **go** .
7. Display a list of the database files. Enter **sp\_helpfile** , then enter **go** .
8. Access the SQL Server master database. Enter **use master** , then enter **go** .
9. Detach the MPWEB database. Enter **sp\_detach\_db 'MPWEB'** , then enter **go** .
10. Decide what you should do with the physical files that you identified in [Step 7](#).
  - These files constitute your detached database. For example, you can archive these files or use them to attach the associated MPWEB database to another SQL Server.
11. Determine the slave database name(s) on your SQL Server. Enter **select name from sysdatabases where name like 'MPWEB%'** , then enter **go** .
12. (Optional) For each additional database named MPWEB\_XX, repeat [Step 6](#) through [Step 10](#) to detach that database, replacing the database name MPWEB with MPWEB\_XX.
  - Note:** The databases are logically linked; therefore, if you want to archive the detached MPWEB database, you must do the same for each MPWEB\_XX database. If you want to reattach the MPWEB database to another SQL Server, you must also reattach the MPWEB\_XX database(s).
13. To exit osql, enter **exit** .

#### Examples: Detaching the Database

In the following examples, the output is displayed for each osql command that is used in the [To Detach the Database](#).

#### Sample Output for Connecting to SQL Server

```
C:> osql -U sa -S SERVERNAME

Password: password

1>
```

#### Sample Output for Accessing the MPWEB Database

```
1> use mpweb

2> go
```

**Sample Output for Displaying a List of Database Files**

In this example, the database MPWEB relies on two physical files: C:\MSSQL2K\Data\MPWEB.mdf and C:\MSSQL2K\Data\MPWEB.ldf.

```

1> sp_helpfile

2> go

name fileid filename filegroup size maxsize growth usage
-----
MPWEBData 1 C:\MSSQL2K\Data\MPWEB.mdf PRIMARY 2432 KB
Unlimited 1024 KB data only

MPWEBLog 2 C:\MSSQL2K\Data\MPWEB.ldf NULL 1280 KB Unlimited
10% log only

```

**Sample Output for Accessing the SQL Server Master Database**

```

1> use master

2> go

```

**Sample Output for Detaching the MPWEB Database**

```

1> sp_detach_db 'MPWEB'

2> go

```

**Sample Output for Determining the Slave Database Name**

In this example, the name of the slave database is MPWEB\_E22AF0EC-805F-45D4-8F76-FB0C6378A5EC-1.

```

1> select name from sysdatabases where name like 'MPWEB%'

2> go

-----

name

[char ]

-----

MPWEB_E22AF0EC-805F-45D4-8F76-FB0C6378A5EC-1

```

**Sample Output for Exiting osql**

```
1> exit
```

```
C:>
```

**To Attach the Database**

Ensure that you have a valid detached MPWEB database, usually, two files named MPWEB.mdf (data file) and MPWEB.ldf (log file), though file names may vary.

1. If the SQL Server to which you want to attach your MPWEB database runs on the Cisco Unified MeetingPlace web server, continue with [Step 2](#).  
or  
If the SQL Server runs on a separate (remote) Windows server, locate that Windows server and log on. If you cannot log on to that Windows server, log on to any Windows-based workstation or server on the network that has a valid installation of SQL Server Client tools, including the osql command, so that you can remotely connect to the SQL Server.
2. Access the command prompt. Choose **Start > Run** , then enter **cmd** .
3. Connect to SQL Server by using osql. Enter **osql -U sa -S server-name** , where *server-name* is the Windows SQL Server to which you want to attach the MPWEB database.  
**Note:** If the SQL Server runs locally, you can omit the *-S server-name* option.
4. Enter your password for the appropriate SA account.  
**Note:** If you are not allowed to connect to this SQL Server as SA, connect by using an account that has enough privileges to attach a database.
5. Determine if a database named MPWEB already exists on this server. Enter **select name from sysdatabases where name = 'MPWEB'** , then enter **go** .
6. If no MPWEB database exists, continue with [Step 7](#).  
or  
If a MPWEB database exists, ensure that it is not being used by an existing Cisco Unified MeetingPlace web server.  
**Note:** You cannot attach a MPWEB database to this SQL Server if an active MPWEB database exists already. Before you proceed, you must detach the existing MPWEB database by completing the [To Detach the Database](#).
7. To verify the installation folder of the SQL Server to which you want to restore this database, check the physical location of the SQL Server master database.  
Enter **sp\_helpfile master** , then enter **go** .  
**Note:** Unless you have a reason to restore your MPWEB database to another disk location, such as for performance and tuning or data recovery reasons, we recommend that you restore the database to the default data folder of this SQL Server installation.
8. Copy the MPWEB.mdf and MPWEB.ldf files under the data folder that you identified in [Step 7](#).
9. Attach the MPWEB database. Enter **sp\_attach\_db 'MPWEB',' data path \MPWEB.mdf',' data path \MPWEB.ldf'** , then enter **go** .
10. (Optional) If you have a valid set of files for the MPWEB\_XX slave database(s), repeat [Step 5](#) through [Step 10](#) for each slave database, replacing MPWEB with MPWEB\_XX to attach that database.
11. To exit osql, enter **exit** .

**Examples: Attaching the Database**

In the following examples, the output is displayed for each osql command that is used in the [To Attach the Database](#).

The following examples use the files MPWEB.mdf and MPWEB.ldf:

**Sample Output for Connecting to SQL Server**

```
C:> osql -U sa -S SERVERNAME

Password: password

1>
```

**Sample Output for Checking if the MPWEB Database Exists**

```
1> select name from sysdatabases where name = 'MPWEB'

2> go

name
-----

(0 row affected)

1>
```

**Sample Output for Checking the Physical Location of the SQL Server Master Database**

In this example, SQL Server Version 2000 is installed in C:\MSSQL2K, and the default data folder is C:\MSSQL2K\data.

```
1> sp_helpfile master

2> go

name filename filegroup size maxsize growth usage
-----

master C:\MSSQL2K\data\master.mdf PRIMARY 15744 KB Unlimited
10% data only

1>
```

**Sample Output for Attaching the MPWEB Database**

```
1> sp_attach_db 'MPWEB', 'data path\MPWEB.mdf', 'data
path\MPWEB.ldf'

2> go
```

### Sample Output for Exiting osql

```
1> exit
```

```
C:>
```

## To Relocate the Database

You may want to relocate the database, putting the Cisco Unified MeetingPlace application and database onto different servers, for example if the server you are using is running out of disk space, or for performance or backup considerations.

1. Detach the MPWEB SQL databases on the existing (for example, local) SQL Server:  
Follow the instructions in [To Detach the Database](#).
2. Attach the MPWEB SQL databases to the new (for example, remote) SQL Server:  
Follow the instructions in [To Attach the Database](#).
3. Change the Database Connection settings on your Cisco Unified MeetingPlace Web Conferencing server to point to the new (in this example, remote) SQL Server:
  1. Double-click the orange door icon in the System Tray.
  2. Click **Web Conferencing**.
  3. Enter the remote SQL server name in the Server field.
  4. Enter the new Username and Password.
  5. Click **OK**.