

Main page: [Cisco Unified MeetingPlace, Release 8.0](#)

Up one level: [Integrations](#)

Note: Multiple clusters are not supported for the IBM Lotus Notes for Cisco Unified MeetingPlace integration.

- [1 Prerequisites for Installing IBM Lotus Notes for Cisco Unified MeetingPlace](#)
- [2 Installing the IBM Lotus Notes for Cisco Unified MeetingPlace Gateway](#)
- [3 How to Configure IBM Lotus Notes for Cisco Unified MeetingPlace for Automatic Authentication](#)
- [4 Preparing to Configure the Mail and Database Templates](#)
- [5 Configuring SSL Support for IBM Lotus Notes](#)
- [6 How to Configure the IBM Lotus Notes Gateway Account to Use the Mail Template](#)
- [7 How to Set up the MeetingPlace Server Agent \(MPSA\) Database for IBM Lotus Notes](#)
- [8 How to Add Cisco Unified MeetingPlace Features to the IBM Lotus Notes Mail Template](#)
- [9 How to Migrate IBM Lotus Notes Users to Cisco Unified MeetingPlace](#)
- [10 How to Customize Meeting Notifications](#)
- [11 Troubleshooting IBM Lotus Notes for Cisco Unified MeetingPlace](#)
- [12 About Upgrading to Cisco Unified MeetingPlace for IBM Lotus Notes Release 8.0 from Release 7.0](#)

Contents

- [1.1 Prerequisites for Installing IBM Lotus Notes for Cisco Unified MeetingPlace](#)
 - ◆ [1.1.1 Restrictions for Using IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0](#)
 - ◆ [1.2 Reviewing System Requirements](#)
 - ◆ [1.3 Gathering Installation Values](#)
 - ◆ [1.4 Creating an IBM Lotus Notes Gateway Account](#)
 - ◇ [1.4.1 Restriction](#)
 - ◇ [1.4.2 Procedure](#)
 - ◇ [1.4.3 What to Do Next](#)
 - ◆ [1.5 Moving the Mail Templates](#)
- [2.2 Installing the IBM Lotus Notes for Cisco Unified MeetingPlace Gateway](#)
 - ◆ [2.1 Restrictions](#)
 - ◆ [2.2 Prerequisites](#)
 - ◆ [2.3 Procedure](#)
 - ◆ [2.4 What to Do Next](#)
- [3.3 How to Configure IBM Lotus Notes for Cisco Unified MeetingPlace for Automatic Authentication](#)
 - ◆ [3.1 Preparing the System for IBM Lotus Domino Authentication](#)
 - ◇ [3.1.1 Before You Begin](#)
 - ◇ [3.1.2 Procedure](#)
 - ◆ [3.2 Importing the User IDs](#)
 - ◇ [3.2.1 Restriction](#)
 - ◇ [3.2.2 Before You Begin](#)
 - ◇ [3.2.3 Procedure](#)

- ◇ [3.2.4 Related Topics](#)
 - ◆ [3.3 Verifying the Import](#)
 - ◇ [3.3.1 Before You Begin](#)
 - ◇ [3.3.2 Procedure](#)
 - ◆ [3.4 Setting the Authentication Method](#)
 - ◇ [3.4.1 Before You Begin](#)
 - ◇ [3.4.2 Procedure](#)
- [4.4 Preparing to Configure the Mail and Database Templates](#)
 - ◆ [4.1 Copying the Mail and Database Templates and Java SSL Files to the IBM Lotus Domino Server](#)
 - ◇ [4.1.1 Before You Begin](#)
 - ◇ [4.1.2 Procedure](#)
 - ◆ [4.2 Setting Up the Database and Mail Templates for IBM Lotus Notes](#)
 - ◇ [4.2.1 Granting Permission to Run Agents on the IBM Lotus Domino Server](#)
 - [4.2.1.1 Before You Begin](#)
 - [4.2.1.2 Procedure](#)
 - ◇ [4.2.2 Signing the MeetingPlace Server Agent \(MPSA\) Database Template](#)
 - [4.2.2.1 Before You Begin](#)
 - [4.2.2.2 Procedure](#)
 - ◇ [4.2.3 Signing the Cisco Unified MeetingPlace Mail Template](#)
 - [4.2.3.1 Before You Begin](#)
 - [4.2.3.2 Procedure](#)
- [5.5 Configuring SSL Support for IBM Lotus Notes](#)
 - ◆ [5.1 Installing the Sun SDK File](#)
 - ◇ [5.1.1 Before You Begin](#)
 - ◇ [5.1.2 Procedure](#)
 - ◆ [5.2 Adding Certificates to the IBM Lotus Domino Keystore](#)
 - ◇ [5.2.1 Before You Begin](#)
 - ◇ [5.2.2 Procedure](#)
 - ◆ [5.3 Editing the java.policy File](#)
 - ◇ [5.3.1 Before You Begin](#)
 - ◇ [5.3.2 Procedure](#)
- [6.6 How to Configure the IBM Lotus Notes Gateway Account to Use the Mail Template](#)
 - ◆ [6.1 Configuring the Account From Cisco Unified MeetingPlace](#)
 - ◇ [6.1.1 Before You Begin](#)
 - ◇ [6.1.2 Procedure](#)
 - ◆ [6.2 Configuring the Account From the IBM Lotus Domino Server](#)
 - ◇ [6.2.1 Before You Begin](#)
 - ◇ [6.2.2 Procedure](#)
- [7.7 How to Set up the MeetingPlace Server Agent \(MPSA\) Database for IBM Lotus Notes](#)
 - ◆ [7.1 Creating the MeetingPlace Server Agent \(MPSA\) Database](#)
 - ◇ [7.1.1 Before You Begin](#)
 - ◇ [7.1.2 Procedure](#)
 - ◆ [7.2 Accessing the Administration Interface for the MeetingPlace Server Agent \(MPSA\) Database](#)
 - ◇ [7.2.1 Before You Begin](#)
 - ◇ [7.2.2 Procedure](#)
 - ◆ [7.3 Assigning Access Control to the MeetingPlace Server Agent \(MPSA\) Database](#)
 - ◇ [7.3.1 Before You Begin](#)
 - ◇ [7.3.2 Procedure](#)
 - ◆ [7.4 Configuring the Design Properties for the MeetingPlace Server Agent \(MPSA\) Database](#)
 - ◇ [7.4.1 Before You Begin](#)
 - ◇ [7.4.2 Procedure](#)

- ◆ 7.5 Adding a Cisco Unified MeetingPlace Profile to the MeetingPlace Server Agent (MPSA) Database
 - ◇ 7.5.1 Before You Begin
 - ◇ 7.5.2 Procedure
- ◆ 7.6 About Replicating the MeetingPlace Server Agent (MPSA) Database
- ◆ 7.7 Modifying the Cisco Unified MeetingPlace Server Settings
 - ◇ 7.7.1 Before You Begin
 - ◇ 7.7.2 Procedure
- ◆ 7.8 Enabling the Admin CleanUp Agent
 - ◇ 7.8.1 Before You Begin
 - ◇ 7.8.2 Procedure
- 8.8 How to Add Cisco Unified MeetingPlace Features to the IBM Lotus Notes Mail Template
 - ◆ 8.1 Modifying the wPreferences Form
 - ◇ 8.1.1 Before You Begin
 - ◇ 8.1.2 Procedure
 - ◆ 8.2 Adding the MPNewPassword Subform
 - ◇ 8.2.1 Before You Begin
 - ◇ 8.2.2 Procedure
 - ◆ 8.3 Adding the MPCalendarEntry and MPNotice Subforms
 - ◇ 8.3.1 Before You Begin
 - ◇ 8.3.2 Procedure
 - ◆ 8.4 Adding the Cisco Unified MeetingPlace Section to the Calendar Entry Form
 - ◇ 8.4.1 Before You Begin
 - ◇ 8.4.2 Procedure
 - ◆ 8.5 Modifying the Calendar Profile Form
 - ◇ 8.5.1 Before You Begin
 - ◇ 8.5.2 Procedure
 - ◆ 8.6 Adding New Cisco Unified MeetingPlace Script Libraries
 - ◇ 8.6.1 Restriction
 - ◇ 8.6.2 Before You Begin
 - ◇ 8.6.3 Procedure
 - ◆ 8.7 Modifying the Notice Form
 - ◇ 8.7.1 Before You Begin
 - ◇ 8.7.2 Procedure
 - ◆ 8.8 Modifying Existing Script Libraries change title
 - ◇ 8.8.1 Restriction
 - ◇ 8.8.2 Before You Begin
 - ◇ 8.8.3 Procedure
 - ◆ 8.9 Adding the MeetingPlace Agent to the Mail Template
 - ◇ 8.9.1 Before You Begin
 - ◇ 8.9.2 Procedure
- 9.9 How to Migrate IBM Lotus Notes Users to Cisco Unified MeetingPlace
 - ◆ 9.1 Migrating a Pilot Group to the Cisco Unified MeetingPlace Mail Template
 - ◇ 9.1.1 Before You Begin
 - ◇ 9.1.2 Procedure
 - ◆ 9.2 Replacing the Standard Mail Template with the Cisco Unified MeetingPlace Mail Template
 - ◇ 9.2.1 Before You Begin
 - ◇ 9.2.2 Procedure
 - ◆ 9.3 How to Update the System to Use the New Template
 - ◇ 9.3.1 Manually Updating a Single System to Use the New Template
 - 9.3.1.1 Before You Begin
 - 9.3.1.2 Procedure

- ◇ 9.3.2 Updating the System to Use the New Template for All Users
 - 9.3.2.1 Before You Begin
 - 9.3.2.2 Procedure
- 10 10 How to Customize Meeting Notifications
 - ◆ 10.1 About Using Multiple Notification Programs
 - ◆ 10.2 About Meeting Notification Formats
 - ◆ 10.3 About Notifications for Rescheduled Meetings
 - ◇ 10.3.1 Notifications for Meetings Rescheduled From IBM Lotus Notes
 - ◇ 10.3.2 Notifications for Meetings Rescheduled From Cisco Unified MeetingPlace
 - ◆ 10.4 About Meeting Notification Templates
 - ◆ 10.5 Customizing the Meeting Notification Templates
 - ◇ 10.5.1 Before You Begin
 - ◇ 10.5.2 Procedure
- 11 11 Troubleshooting IBM Lotus Notes for Cisco Unified MeetingPlace
 - ◆ 11.1 Troubleshooting: What to Do First
 - ◇ 11.1.1 Verifying That the Windows Services Are Running
 - 11.1.1.1 Restriction
 - 11.1.1.2 Before You Begin
 - 11.1.1.3 Procedure
 - ◇ 11.1.2 Verifying That MPNotify and MPAgent Can Sign In
 - 11.1.2.1 Restriction
 - 11.1.2.2 Before You Begin
 - 11.1.2.3 Procedure
 - ◇ 11.1.3 Checking the Windows Event Viewer for Errors
 - 11.1.3.1 Before You Begin
 - ◆ 11.2 Resolving Error Messages
 - ◇ 11.2.1 Resolving Error Messages Related to Joining Meetings
 - 11.2.1.1 Related Topics
 - ◇ 11.2.2 Resolving Error Messages Related to Scheduling Problems
 - 11.2.2.1 Before You Begin
 - 11.2.2.2 Procedure
 - 11.2.2.3 Related Topics
 - ◇ 11.2.3 Resolving Error Messages Related to Incorrect Profile Information
 - ◇ 11.2.4 Resolving Error Messages Related to System Setup
 - ◇ 11.2.5 Resolving Error Messages Related to Errors Validating a User Agent Execution Access
 - ◇ 11.2.6 Resolving Error Messages Related to Java AccessControl
 - ◇ 11.2.7 Resolving Error Messages Related to the Connection Between Cisco Unified MeetingPlace and IBM Lotus Domino
 - 11.2.7.1 Before You Begin
 - 11.2.7.2 Procedure
 - 11.2.7.3 Related Topics
 - ◇ 11.2.8 JavaScript Error Messages When Selecting the URL to Attend the Meeting
 - ◆ 11.3 Troubleshooting Mail Template Settings
 - ◇ 11.3.1 Procedure
 - ◇ 11.3.2 Related Topics
 - ◆ 11.4 Resolving Scheduling Errors When the "Allow Internet Access" Option is Checked
 - ◆ 11.5 Resolving Problems when LNNotify Does not Start
 - ◆ 11.6 Resolving Java.io.fileNotFound Exception
 - ◇ 11.6.1 Before You Begin
 - ◇ 11.6.2 Procedure
 - ◇ 11.6.3 Related Topics
 - ◆ 11.7 Resolving Cross Certify Errors

- ◆ [11.8 Problems with Meeting Attachments](#)
 - ◇ [11.8.1 Before You Begin](#)
 - ◇ [11.8.2 Procedure](#)
- ◆ [11.9 Problems With Meeting Notifications](#)
 - ◇ [11.9.1 Before You Begin](#)
 - ◇ [11.9.2 Procedure](#)
 - ◇ [11.9.3 Procedure](#)
- ◆ [11.10 Problem Accessing Online Help From the "About This Database" Page](#)
- [12.12 About Upgrading to Cisco Unified MeetingPlace for IBM Lotus Notes Release 8.0 from Release 7.0](#)
 - ◆ [12.1 Restrictions](#)
 - ◆ [12.2 Before You Begin](#)
 - ◆ [12.3 Procedure](#)

1 Prerequisites for Installing IBM Lotus Notes for Cisco Unified MeetingPlace

- [Restrictions for Using IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0](#)
- [Reviewing System Requirements](#)
- [Gathering Installation Values](#)
- [Creating an IBM Lotus Notes Gateway Account](#)
- [Moving the Mail Templates](#)

Restrictions for Using IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0

Be sure to communicate the following restrictions to the users who schedule meetings from the IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0 integration:

- You cannot use the IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0 integration with deployments that use Cisco WebEx for scheduling. For a description of the different web deployments, see the *Planning Guide for Cisco Unified MeetingPlace Release 8.0* at: [http://docwiki.cisco.com/wiki/Cisco Unified MeetingPlace%2C Release 8.0 -- Planning Your Deployment](http://docwiki.cisco.com/wiki/Cisco_Unified_MeetingPlace%2C_Release_8.0_-_Planning_Your_Deployment)
- Any invitees you add when scheduling from the Lotus Notes client do not display when viewing meeting details from the end-user web interface.
- The method of attending option to ?Have system find user? is not supported for users who are invited to a meeting from Lotus Notes.
- IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0 has the following limitations on the number of occurrences of repeating meetings that users can schedule:

Meeting recurrence	Maximum number of meetings
Daily	200
Weekly	100
Bi-weekly	50
Monthly	23

Reviewing System Requirements

Before installing IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0, read the *System Requirements for Cisco Unified MeetingPlace Release 8.0* at

[http://doewiki.cisco.com/wiki/Cisco Unified MeetingPlace Release 8.0 -- System Requirements for Cisco Unified MeetingPlace Release 8.0](http://doewiki.cisco.com/wiki/Cisco_Unified_MeetingPlace_Release_8.0_-_System_Requirements_for_Cisco_Unified_MeetingPlace_Release_8.0)

Gathering Installation Values

Gather and record the information below to prepare for your installation of IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0.

Description	Your Value
<p>The location of the notes.ini file for your IBM Lotus Notes account. This file is usually in C:\Lotus\Notes or C:\Program Files\Lotus\Notes.</p> <p>Note: You must already have run the IBM Lotus Notes client (that is, opened the client, connected to the IBM Lotus Domino Server, and closed the client) to create the notes.ini file.</p> <p>Note: The installation program only prompts you for the location of this file if it cannot find it or if it detects more than one .ini file on your system.</p>	
<p>Hostname, IP address, or FQDN of the <i>internal</i> Cisco Unified MeetingPlace Web Server.</p>	
<p>Hostname, IP address, or FQDN of the <i>external</i> Cisco Unified MeetingPlace Web Server.</p>	
<p>Password for the IBM Lotus Notes account on the IBM Lotus Domino Server.</p>	
<p>URL for the internal Cisco Unified MeetingPlace Web Server (required for the click-to-attend links).</p>	
<p>URL for the external Cisco Unified MeetingPlace Web Server (required for the click-to-attend links).</p> <p>If you did not install an external Web Server, enter the URL for the internal Web Server.</p>	

Creating an IBM Lotus Notes Gateway Account

This topic describes how to create an account for the Cisco Unified MeetingPlace for IBM Lotus Notes integration gateway on the Lotus Domino Server. The integration gateway uses this account to access IBM Lotus Notes and to send back-end notifications. You will require a corresponding account on the Cisco Unified MeetingPlace Application Server to ensure the proper functioning of attachments between the Domino and MeetingPlace servers.

Tip:

- If you have more than one Cisco Unified MeetingPlace Application Server, each with its own installation of IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0, create an IBM Lotus Notes gateway account for each installation with a unique identifying name, such as MP-Boston or MP-Atlanta.
- If you have created an IBM Lotus Domino server cluster, the MeetingPlace Server Agent (MPSA) database should be created on the Domino server that hosts the IBM Lotus Notes account used for

the MeetingPlace integration. After that, MPSA has to be replicated to all Domino servers in the cluster.

- Front-end notifications will go through the respective Domino server directly to MeetingPlace Web server. However, all back-end notifications will be sent through only one Domino server, the one that holds the Cisco Unified MeetingPlace Gateway user mailbox (the Domino that is specified in the MeetingPlace integration).
- On the IBM Lotus Domino side, a user requires only regular user permissions for the IBM Lotus Notes account for the IBM Lotus Notes with Cisco Unified MeetingPlace Gateway.

Restriction

You must have Administrator permissions on the IBM Lotus Domino Server.

Procedure

1. Sign in to the IBM Domino Administrator.
2. Select the tab with the name of your domain (for example, CISCO_Domain).
3. Select the **People & Groups** tab from the Domain tab.
4. Select **People** from the left pane of the People & Groups tab.
5. In the right pane of the People and Groups tab, select the arrow next to the **People** icon to expand the drop-down menu, then choose **Register**.
The system displays the Choose a Certifier window if this is the first time that you are registering a new account.
6. Locate and choose the cert.id file.
 - ◆ The default certifier ID is in C:\Program Files\IBM\Lotus\Notes\Domino\Data.
 - ◆ If the path to the cert.id file does not appear next to the Certifier ID button, select **Certifier ID** to open the Choose Certifier ID window.
7. Select **Open**.
8. Select **OK** in the Choose a Certifier window when the cert.id file path is correct.
9. Enter a new password for the certifier ID.
The system displays the Register Person window.
10. Check **Advanced** to display all options on the page.
11. Enter **MeetingPlace** in the Last name field.
We recommend that you leave the First name field blank. The system automatically populates the ShortName field, based on the First name and Last name values. The value in the ShortName field is used to name the mail database for this user account (for example, mail/MeetingPlace).
12. Enter your password for this account.
13. Select **Password Options**.
14. Adjust your Password Quality Scale in the Password Options window.
15. Check **Set internet password**.
16. Select **OK**.
17. Select **Mail**.
18. Choose **Manager** from the Mail file owner access drop-down list.
19. From the Mail file template list, choose the mail template that you want to associate with this account:

Name in the Mail file template list	Associated mail template
Mail(R8.5)	mail85.ntf
Mail(R8)	mail8.ntf
Mail(R7)	mail7.ntf
Mail(R6.5)	mail65.ntf
Mail(R6)	mail6.ntf

20. Select the green checkmark button to add this user to the registration queue.

21. Select **Register**.

22. Select **Done**.

What to Do Next

Make sure that you create a corresponding account on the Cisco Unified MeetingPlace Application Server. The corresponding account must have the same username, password, and email address as you configured for the gateway account on the Lotus Domino Server. If you do not create a corresponding user account on the MeetingPlace server, attachments between the Domino Server and MeetingPlace server will fail.

Moving the Mail Templates

Move your standard IBM Lotus Notes mail template to another directory to avoid causing confusion between this standard mail template and the Cisco Unified MeetingPlace mail templates. The name of your mail template is as follows:

IBM Lotus Domino Release	Name of Mail Template
Release 6	mail6.ntf
Release 6.5	mail65.ntf
Release 7	mail7.ntf
Release 8	mail8.ntf
Release 8.5	mail85.ntf

2 Installing the IBM Lotus Notes for Cisco Unified MeetingPlace Gateway

Restrictions

- You must install the IBM Lotus Notes for Cisco Unified MeetingPlace gateway on the same hardware and in the same directory as the Cisco Unified MeetingPlace Web Server software. For example, if you install the Web Server software in the C:\Program Files\Cisco Systems directory, you must also install IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0 integration in that directory.
- Passwords in the IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0 installer are case-sensitive.

Prerequisites

- Complete all the tasks in the [1 Prerequisites for Installing IBM Lotus Notes for Cisco Unified MeetingPlace](#).
- You must have a user ID with administrator privileges to sign in to the Cisco Unified MeetingPlace Web Server.
- Install the applicable release of the IBM Lotus Notes client, which depends on the release of IBM Lotus Domino Server that you use.

Procedure

1. Insert the IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0 CD into the CD or DVD-ROM drive on the Cisco Unified MeetingPlace Web Server.
2. Double-click the setup.exe file.
3. Follow the instructions in the InstallShield wizard keeping the following in mind:
 - ◆ You created the notes.ini file for the gateway account in the [Creating an IBM Lotus Notes Gateway Account](#). The system leaves the path blank if the installer cannot find or detects more than one notes.ini file on your system.
 - ◆ You also created the password for the gateway account in the [Creating an IBM Lotus Notes Gateway Account](#).
4. Select **Finish** on the last screen.

The system restarts the server.

What to Do Next

If your Cisco Unified MeetingPlace deployment includes two web servers or allows users to access external Cisco Unified MeetingPlace web meetings from their Lotus Notes client, install the Notes Gateway on the external server or manually copy all 33 Notes-related template files from the internal server located at C:\Program Files\Cisco Systems\MPWeb\Template to the same location on the external server.

3 How to Configure IBM Lotus Notes for Cisco Unified MeetingPlace for Automatic Authentication

You can improve the speed of the meeting scheduling process by configuring your IBM Lotus Domino Server to automatically authenticate users to Cisco Unified MeetingPlace. With automatic authentication, the IBM Lotus Domino Server can pass user IDs to Cisco Unified MeetingPlace for verification whenever a user schedules a meeting. If the user IDs on both systems match, the system automatically signs users in to Cisco Unified MeetingPlace.

Without automatic authentication, users must enter their Cisco Unified MeetingPlace user IDs and passwords in the calendar entry form when they schedule a Cisco Unified MeetingPlace meeting.

- [Preparing the System for IBM Lotus Domino Authentication](#)
- [Importing the User IDs](#)
- [Verifying the Import](#)

- Setting the Authentication Method

Preparing the System for IBM Lotus Domino Authentication

Before You Begin

You must have a user ID with administrator privileges to sign in to the Cisco Unified MeetingPlace Web Server.

Procedure

1. Sign in to the Cisco Unified MeetingPlace Web Server as an administrator.
2. Select **Start > Control Panel > Administrative Tools > Component Services**.
3. Select **console root > Component Services > Computers > My Computer > DCOM Config > LNNotify** from the left pane.
4. Right-click **LNNotify**.
5. Select **Properties**.
6. Select the Security tab.
7. Select **Customize** from Launch and Activation Permissions.
8. Select **Edit**.
9. Highlight the user ID called Local Service.
10. Grant the Local Service user ID Local Launch and Local Activation permissions.
11. Select **OK** twice.

Importing the User IDs

Restriction

You must configure Cisco Unified MeetingPlace to use only Cisco Unified MeetingPlace authentication before you can enable IBM Lotus Domino authentication because IBM Lotus Notes does not support other authentication methods, such as Windows Integrated Authentication (WIA). For information on authentication, see the *Configuration Guide for Cisco Unified MeetingPlace Release 8.0* or the online help in the administrator interface.

Before You Begin

You must have a user ID with administrator privileges to sign in to the IBM Lotus Domino Server.

Procedure

1. Sign in to the IBM Lotus Domino Server as an administrator.
2. Use one of the following methods to enter Cisco Unified MeetingPlace user IDs:
 - ◆ Import the Cisco Unified MeetingPlace user IDs.

- ◆ Import the IBM Lotus Domino address book ShortName field into the Cisco Unified MeetingPlace profile of each user as their user ID.

Note: Although any IBM Lotus Domino address book field can contain a Cisco Unified MeetingPlace user ID, we recommend using the ShortName field because it contains unique values, and has configurable security settings. If you decide to use another field that contains multiple values, make sure that the Cisco Unified MeetingPlace user ID is listed first. By default, Cisco Unified MeetingPlace uses the first value in the field for authentication.

3. Set the security option in the ShortName field to **Must Have at Least Editor Access to Use**. This prevents users from changing their user IDs and signing in to Cisco Unified MeetingPlace as someone else.

Related Topics

For information about how to import Cisco Unified MeetingPlace user IDs, see the "Raw Data Export and Import Specifications" module in the *Configuration Guide for Cisco Unified MeetingPlace Release 8.0* at http://www.cisco.com/en/US/products/sw/ps5664/ps5669/products_installation_and_configuration_guides_list.html

Verifying the Import

Before You Begin

You must have a user ID with administrator privileges to sign in to the Cisco Unified MeetingPlace Web Server.

Procedure

1. Sign in to the Cisco Unified MeetingPlace Web Server.
2. Open the Gateways Configuration utility.
3. Select the **Notes Gateway** tab.
4. Verify that the authentication field contains the Cisco Unified MeetingPlace user IDs.
5. Close the Gateway Configuration utility.

Setting the Authentication Method

Before You Begin

You must have user IDs with administrator privileges to sign in to the IBM Lotus Domino Server, IBM Lotus Notes Server, and Cisco Unified MeetingPlace Administration Center.

Procedure

1. Sign in to the IBM Lotus Domino Server as an administrator.
2. Open the MeetingPlace Server Agent (MPSA) database.

3. Select **Use Domino Authentication**.
4. Select **Save**.
5. Select **Close**.
6. Open a web browser.
7. Connect to the Cisco Unified MeetingPlace Web Server by entering **http://'hostname'**, where *hostname* is the hostname of the internal Web Server.
8. Select **Sign In**.
9. Enter an administrator username and password.
10. Select **Admin**.
11. Select **Web Server**.
12. From the Web Server Administration page, select the name of your server on the bottom half of the page. Server information populates the top half of the page.
13. Choose **Yes** in **Set Trust Web Server Authentication**.
14. Select **Web Server Name** in the View area.
15. Scroll to the Web Authentication area.
16. Choose **Web Page Form** in Step 2: Login Method.
17. Select **Submit**.
18. Exit Cisco Unified MeetingPlace.

Tip: After you synchronize the user IDs on Cisco Unified MeetingPlace and IBM Lotus Domino, you can develop a process to ensure that all new users have a Cisco Unified MeetingPlace profile. By developing scripts and using the Cisco Unified MeetingPlace import capabilities, you can automate this process so that IBM Lotus Domino and Cisco Unified MeetingPlace are synchronized. For information about how you can use scripts to update the Cisco Unified MeetingPlace database, contact Cisco Technical Support.

4 Preparing to Configure the Mail and Database Templates

- [Copying the Mail and Database Templates and Java SSL Files to the IBM Lotus Domino Server](#)
- [Setting Up the Database and Mail Templates for IBM Lotus Notes](#)

Copying the Mail and Database Templates and Java SSL Files to the IBM Lotus Domino Server

Copy the mail and database templates and the Java SSL files to the IBM Lotus Domino Server data directory where they will be used to set up the database and templates on your Cisco Unified MeetingPlace Web Server. These files are located in the *drive:\Program Files\Cisco Systems\Cisco MeetingPlace for Notes\Files* directory.

File	Description
MPSA.ntf	The database template.
MPSA_SSL.ntf	<ul style="list-style-type: none"> • Use the file called MPSA.ntf if you do <i>not</i> want to set up SSL support. • Use the file called MPSA_SSL.ntf if you <i>do</i> want to set up SSL support.

mailxx_xxMP.ntf	<p>The Cisco Unified MeetingPlace mail template for the version of IBM Lotus Notes that you are using:</p> <ul style="list-style-type: none"> • mail60_05MP.ntf • mail65_5MP.ntf • mail65_6MP.ntf • mail70_2MP.ntf • mail70_3MP.ntf • mail80_01MP.ntf • mail80_0MP.ntf • mail85_0MP.ntf
<p>jcrt.jar</p> <p>jnet.jar</p> <p>jsse.jar</p>	<p>Additions to the Java setup for IBM Lotus Domino. These files allow you to support SSL.</p>

Before You Begin

- Sign in to the Cisco Unified MeetingPlace Application Server as an administrator.
- Use FTP to connect to the IBM Lotus Domino Server.
- Sign in to the IBM Lotus Domino Server with a user ID that has rwx privileges in the Lotus\Domino\Data directory.

Procedure

1. Copy the following files to your IBM Lotus Domino Server:
 - ◆ If you do *not* want to set up SSL support, copy the MPSA.ntf and mailxx_xxMP.ntf files to the Lotus\Domino\Data directory on your IBM Lotus Domino Server.
 - ◆ If you *do* want to set up SSL support, copy the MPSA_SSL.ntf and mailxx_xxMP.ntf files to the Lotus\Domino\Data directory on your IBM Lotus Domino Server. Copy the three Java extension files (jcrt.jar, jnet.jar, jsse.jar) to the Lotus\Domino\jvm\lib\ext directory on your IBM Lotus Domino Server.
2. Enter **Exit** at the console command prompt.
3. Choose **Start > Programs > Lotus Applications > Domino Server** to restart the IBM Lotus Domino Server.

Setting Up the Database and Mail Templates for IBM Lotus Notes

- [Granting Permission to Run Agents on the IBM Lotus Domino Server](#)
- [Signing the MeetingPlace Server Agent \(MPSA\) Database Template](#)
- [Signing the Cisco Unified MeetingPlace Mail Template](#)

Granting Permission to Run Agents on the IBM Lotus Domino Server

Agents are the background processes in the IBM Lotus Notes for Cisco Unified MeetingPlace plug-in that run on the IBM Lotus Domino Server. You must grant permission so that the agents can run on the server.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Administrator.
- Select your Domain tab (for example, CISCO_Domain).

Procedure

1. Select **Configuration**.
2. Expand the **Server** view.
3. Select **Current Server Document**.
4. Select **Security** in the right pane.
5. Double-click the page to bring it in to edit mode.
6. Scroll to the right until you see the Programmability Restrictions area.
7. In the Who Can column next to the following restrictions, add MeetingPlace to give yourself these permissions:
 - ◆ Run unrestricted methods and operations
 - ◆ Run restricted LotusScript/Java agents
8. Select **Save & Close**.

Signing the MeetingPlace Server Agent (MPSA) Database Template

You must sign the MeetingPlace Server Agent (MPSA) database template to verify that it has permissions to run agents on the IBM Lotus Domino Server.

Before You Begin

- Copy the MeetingPlace Server Agent (MPSA) database template to the IBM Lotus Domino Server. See the [Copying the Mail and Database Templates and Java SSL Files to the IBM Lotus Domino Server](#).
- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Administrator.
- Select your Domain tab (for example, CISCO_Domain).

Procedure

1. Select **Files**.
2. Choose **Templates Only**.

3. Right-click the file name of the MeetingPlace Server Agent (MPSA) database template (either MPSA.ntf or MPSA_SSL.ntf).
4. Choose **Sign**.
5. Select **All Design Documents**.
6. Select **OK**.

Signing the Cisco Unified MeetingPlace Mail Template

Before You Begin

- Copy the mail template to the IBM Lotus Domino Server. See the [Copying the Mail and Database Templates and Java SSL Files to the IBM Lotus Domino Server](#).
- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Administrator.
- Select your Domain tab (for example, CISCO_Domain).

Procedure

1. Select **Files**.
2. Choose **Templates Only**.
3. Right-click the file name of the Cisco Unified MeetingPlace mail template (such as mail65_5MP.ntf or mail70_2MP.ntf).
4. Choose **Sign**.
5. Select **OK**.

Note: To access the Cisco Unified MeetingPlace mail template from other IBM Lotus Domino Servers, replicate the mail template file to those servers. See the IBM Lotus Domino documentation for information about replicating files.

5 Configuring SSL Support for IBM Lotus Notes

Secure Socket Layer (SSL) increases the security of your transmissions by enabling HTTPS encryption. For HTTPS encryption to function properly, you must configure both IBM Lotus Domino and Cisco Unified MeetingPlace for SSL authentication. If you have a Lotus Domino cluster with multiple servers, repeat the procedures in this section for each of the Lotus Domino servers in the cluster containing an MPSA database. See the *Configuration Guide for Cisco Unified MeetingPlace Release 8.0* or the online help in the administrator interface for information on configuring SSL support for Cisco Unified MeetingPlace.

- [Installing the Sun SDK File](#)
- [Adding Certificates to the IBM Lotus Domino Keystore](#)
- [Editing the java.policy File](#)

Installing the Sun SDK File

The Sun SDK file provides the keytool.exe tool which is used for importing certificates.

Before You Begin

- Copy the three .jar files onto your IBM Lotus Domino Server. See the [Copying the Mail and Database Templates and Java SSL Files to the IBM Lotus Domino Server](#).
- Sign in to the IBM Lotus Domino Server as an administrator.

Procedure

1. Open a web browser.
2. Navigate to <http://java.sun.com/j2se/1.4.2/download.html>.
3. Select **Download J2SE SDK**.
4. Select a platform.
5. Check **I agree to the Java 2 Software Development Kit (J2SDK) Standard Edition 1.4.2 License Agreement**.
6. Select **Continue**.
7. Choose a download file from the Windows Platform area.
8. Follow the prompts until the file is completely downloaded.

Adding Certificates to the IBM Lotus Domino Keystore

After you obtain your certificates, use the keytool.exe tool to add the certificates to the list of trusted certificates (which is also called your keystore) on your IBM Lotus Domino Server. Your keystore is the cacerts file in the Lotus\Domino\jvm\lib\security directory of your IBM Lotus Domino Server.

For more information about obtaining certificates, see the *Configuration Guide for Cisco Unified MeetingPlace Release 8.0* or the online help in the administrator interface.

Before You Begin

Sign in to the Cisco Unified MeetingPlace Web Server as an administrator.

Procedure

1. Use FTP or a similar program to copy your certificate file from the Cisco Unified MeetingPlace Web Server to the IBM Lotus Domino Server.
2. Sign in to the IBM Lotus Domino Server as an administrator.
3. Choose **Start > Run**.
4. Enter **cmd**.

5. Select **OK**.
6. Enter the following command, replacing values as indicated below:

```
<path>\jre\bin\keytool -import -alias [any_alias] -file [your_certificate.cer] -keystore [cacerts]
```

Replace	With
path	The path to your Java SDK files (for example, c:\j2sdk1.4.2_03)
any_alias	The alias that you are applying to the certificate (for example, WebHomePageCertificate). This is how your certificate will be listed in the keystore.
your_certificate.cer	The path to your .cer file for the Home Page hostname (for example, c:\temp\webhomepage.cer)
cacerts	The path to the cacerts file on your IBM Lotus Domino Server (for example, c:\Lotus\Domino\jvm\lib\security\cacerts). cacerts is the name of your keystore.

For example:

```
c:\j2sdk1.4.2_03\jre\bin\keytool -import -alias
Ciscocertificate -file c:\temp\newcertificate.cer -keystore
c:\Lotus\Domino\jvm\lib\security\cacerts
```

Note: Enter the default password, **changeit**, if your IBM Lotus Domino cacerts file requires a password.

7. Enter **yes** at the IBM Lotus Notes client prompt.
8. Repeat Step 6, replacing *any_alias* with a new alias and replacing *your_certificate.cer* with the path to your .cer file for the server hostname.
9. Repeat Step 7.
10. Close the command-line interface.

Editing the java.policy File

The java.policy file contains permissions to set the system properties. Edit this file to enable the MeetingPlace Server Agent (MPSA) database to be able to communicate over HTTPS with the IBM Lotus Notes for Cisco Unified MeetingPlace gateway.

Before You Begin

Sign in to the IBM Lotus Domino Server as an administrator.

Procedure

1. Navigate to *drive:\Lotus\Domino\jvm\lib\security*.
2. Double-click the *java.policy* file to open it in Notepad.
3. Add the following line to the end of the file just before the closing brace (which looks like this `};`):
permission java.util.PropertyPermission "java.protocol.handler.pkgs", "write";
4. Save and close the file.

6 How to Configure the IBM Lotus Notes Gateway Account to Use the Mail Template

In the [Creating an IBM Lotus Notes Gateway Account](#), you created a dedicated account that will be used to access IBM Lotus Notes and to send back-end notifications.

Configure this account to use the Cisco Unified MeetingPlace mail template that you set up in the [Setting Up the Database and Mail Templates for IBM Lotus Notes](#).

Perform *either* of the following two procedures:

- [Configuring the Account From Cisco Unified MeetingPlace](#)
- [Configuring the Account From the IBM Lotus Domino Server](#)

Configuring the Account From Cisco Unified MeetingPlace

Note: You only need to perform one procedure: either this one or the procedure in the [Configuring the Account From the IBM Lotus Domino Server](#).

Before You Begin

Sign in to the Cisco Unified MeetingPlace Web Server as an administrator.

Procedure

1. Choose **Start > Control Panel > Administrative Tools > Services**.
2. Stop the Cisco Unified MeetingPlace Notification Gateway service called MPNotify.
Note: The Cisco Unified MeetingPlace for Notes Gateway service (called LNNotify) also stops when you stop MPNotify. For information about stopping services, see the *Configuration Guide for Cisco Unified MeetingPlace Release 8.0* or the online help in the administrator interface.
3. Open IBM Lotus Notes.
4. Select **Calendar**.
5. Choose **File > Database > Replace Design**.
6. Choose the IBM Lotus Domino Server that contains your Cisco Unified MeetingPlace templates.
7. Choose your Cisco Unified MeetingPlace mail template.

8. Select **Replace**.
9. Complete the following steps:
 1. Choose **Tools > Preferences**.
 2. Select **MeetingPlace**.
 3. Enter a username and password.
 4. Choose a default server.
 5. Select **OK**.
10. Restart the LNNotify and MPNotify services.

Configuring the Account From the IBM Lotus Domino Server

Note: You only need to perform one procedure: either this one or the procedure in the [Configuring the Account From Cisco Unified MeetingPlace](#).

Before You Begin

Sign in to the IBM Lotus Domino Server as an administrator.

Procedure

1. Open a command-line interface window on the IBM Lotus Domino Server.
2. Enter the following command:

```
load convert mail/mail_database * mail_template
```

Variable	Description
<i>mail_database</i>	The name of your mail database on the Web Server, for example, meetingplace.nsf.
<i>mail_template</i>	The name of your Cisco Unified MeetingPlace mail template, for example, mail65_5mp.ntf.

Note: If you create another IBM Lotus Notes user, specify the Cisco Unified MeetingPlace mail template (mailxx_xmp.ntf) you chose in this procedure as the default mail template.

7 How to Set up the MeetingPlace Server Agent (MPSA) Database for IBM Lotus Notes

The MeetingPlace Server Agent (MPSA) database, called MPSA.nsf, enables all communication between IBM Lotus Notes and Cisco Unified MeetingPlace. Use the MPSA.ntf template (or the MPSA_SSL.ntf template if you are using SSL) as the basis for the new database.

Tip: Files with the .nsf suffix are databases and files with the .ntf suffix are database *templates*.

- [Creating the MeetingPlace Server Agent \(MPSA\) Database](#)
- [Accessing the Administration Interface for the MeetingPlace Server Agent \(MPSA\) Database](#)
- [Assigning Access Control to the MeetingPlace Server Agent \(MPSA\) Database](#)
- [Configuring the Design Properties for the MeetingPlace Server Agent \(MPSA\) Database](#)
- [Adding a Cisco Unified MeetingPlace Profile to the MeetingPlace Server Agent \(MPSA\) Database](#)
- [About Replicating the MeetingPlace Server Agent \(MPSA\) Database](#)
- [Modifying the Cisco Unified MeetingPlace Server Settings](#)
- [Enabling the Admin CleanUp Agent](#)

Creating the MeetingPlace Server Agent (MPSA) Database

Before You Begin

Open IBM Lotus Domino Administrator.

Procedure

1. Choose **File > Application > New**.
2. Choose the name of the IBM Lotus Domino Server to which you are signed in. The server is the location for the new database.
3. Enter **MeetingPlace Server Agent** for the title.
4. Enter **MPSA.nsf** for the file name.
5. Choose the IBM Lotus Domino Server that contains your database template.
6. Choose **MeetingPlace Server Agent** from the list of available templates.
7. Check **Inherit future design changes**.
8. Select **OK**.
9. With the newly created MeetingPlace Server Agent database open, choose **File > Application > Access Control**.
10. Choose **Default** from the list of Access Control List entries.
11. Select at least **Editor** access in the Access field.

Accessing the Administration Interface for the MeetingPlace Server Agent (MPSA) Database

Before You Begin

Perform the procedure in the [Creating the MeetingPlace Server Agent \(MPSA\) Database](#).

Procedure

1. Select the tab with your domain name, for example, CISCO_Domain.
2. Choose **File > Application > Open**.
3. Choose your IBM Lotus Domino Server from the Open Application window.

4. Enter **MPSA.nsf** for the file name.
5. Select **Open**.
6. If a new tab opens, select the **X** in the corner to close it.
7. Select **Administration** from the left pane of the MeetingPlace Server Agent window.
8. Select **Edit/Create Profile Document** from the right pane.

You are now in the Administration Interface.

Assigning Access Control to the MeetingPlace Server Agent (MPSA) Database

Assign access control to the MeetingPlace Server Agent (MPSA) database to give users permissions to access the database.

Before You Begin

Perform the procedure in the [Creating the MeetingPlace Server Agent \(MPSA\) Database](#).

Procedure

1. Select the tab with your domain name, for example, CISCO_Domain.
2. Select **Files**.
3. Choose **Databases Only** from the Show Me field on the top right.
4. Choose **MeetingPlace Server Agent**. If you do not see the MeetingPlace Server Agent database in your list of databases, refresh the page.
5. Right-click the database.
6. Choose **Access Control > Manage**.
The system opens the Access Control List window. The accounts are listed in the center of the window below People, Servers, Groups.
7. Choose **Default**.
8. Highlight **Author** for the Default account in the Access field.
9. Select **MeetingPlace** from the account list.
10. Highlight **Manager** from the Access field. Keep the MeetingPlace account highlighted.
11. Verify in the **Roles** area in the bottom-right corner that the Administrator role is checked.
12. Perform the following actions if the Administer role is not listed:
 1. Select **Roles**.
 2. Highlight **Administrator**.
 3. Select **Add**.
 4. Go back to the Basics tab and select **Administrator**.
13. Select **OK**.

Configuring the Design Properties for the MeetingPlace Server Agent (MPSA) Database

Before You Begin

Perform the procedure in the [Assigning Access Control to the MeetingPlace Server Agent \(MPSA\) Database](#).

Procedure

1. Select the MeetingPlace Server Agent database from the Files tab.
2. Choose **File > Application > Properties**.
3. Select the tab that sets the design properties.
4. Verify that the following parameters are unchecked:
 - ◆ List in Database Catalog
 - ◆ Show in 'Open Database' dialog

Adding a Cisco Unified MeetingPlace Profile to the MeetingPlace Server Agent (MPSA) Database

To schedule meetings from IBM Lotus Notes, you must provide the MeetingPlace Server Agent (MPSA) database with the URLs of the Cisco Unified MeetingPlace internal and external Web Servers.

Before You Begin

Perform the procedure in the [Configuring the Design Properties for the MeetingPlace Server Agent \(MPSA\) Database](#).

Procedure

1. Update your Cisco Unified MeetingPlace account with the permissions you assigned earlier by closing and reopening the MeetingPlace Server Agent database.
2. Choose **File > Application > Open**.
3. Choose your IBM Lotus Domino Server.
4. Enter **MPSA.nsf** for the file name.
5. Select **Open**.
6. If a new tab opens, select the **X** in the corner to close it.
7. Select **Administration** in the left pane.
8. Choose **Edit/Create Profile Document** in the right pane.
9. Select **Add Server**.
10. Fill in the following fields:

Parameter	Description
MeetingPlace Server Name	The name of the Cisco Unified MeetingPlace Web Server that you want users to see on the Calendar Entry form when they schedule a meeting.
MeetingPlace Web CGI URL	The URL of the internal Web Server in the format <code>http://host_name/mpweb/scripts/mpx.dll</code> , where <i>host_name</i> is the hostname or IP address of the internal Cisco Unified MeetingPlace Web Server.
External MeetingPlace Web CGI URL	The URL of the external Web Server in the format <code>http://host_name/mpweb/scripts/mpx.dll</code> , where <i>host_name</i> is the hostname or

	IP address of the external Cisco Unified MeetingPlace Web Server.
Notes Account for MeetingPlace	<p>The name of the IBM Lotus Notes account for Cisco Unified MeetingPlace on the IBM Lotus Domino Server. For example, you can call this account MPNotes.</p> <p>Entering this account name allows the IBM Lotus Domino Server to transfer meeting attachments to Cisco Unified MeetingPlace. The attachments are forwarded to the Cisco Unified MeetingPlace Application Server. Participants can then access meeting attachments from Cisco Unified MeetingPlace.</p> <p>Note: Make sure that you have also created a corresponding profile for the IBM Lotus Notes account on the Cisco Unified MeetingPlace Application Server. This profile is required for the Application Server to authenticate the IBM Lotus Notes for Cisco Unified MeetingPlace gateway and allow it to transfer meeting attachments. This profile must match the name you used for the IBM Lotus Notes account on the IBM Lotus Domino Server that you created in the Creating an IBM Lotus Notes Gateway Account, for example, MPNotes.</p>
Use SSL (https) Note: There are two boxes: one next to the MeetingPlace Web CGI URL field and one next to the External MeetingPlace Web CGI URL field.	Check these boxes if you are using the SSL version of the template.

11. Select **OK**.
12. Choose **Save and Close**.
13. Repeat Steps 9 through 12 for each additional Cisco Unified MeetingPlace Web Server.

About Replicating the MeetingPlace Server Agent (MPSA) Database

If you have multiple IBM Lotus Domino Servers, use the Replication feature to replicate the MeetingPlace Server Agent (MPSA) database to the other IBM Lotus Domino Servers. See the online help for IBM Lotus Notes for information on doing this.

Modifying the Cisco Unified MeetingPlace Server Settings

The toolbar at the top of the Cisco Unified MeetingPlace system profile document allows you to add Cisco Unified MeetingPlace Web Servers and modify or delete existing ones. You added the Cisco Unified MeetingPlace system profile document in the [Adding a Cisco Unified MeetingPlace Profile to the MeetingPlace Server Agent \(MPSA\) Database](#).

When you add a Cisco Unified MeetingPlace Web Server, users can choose it from the server list display on the IBM Lotus Notes calendar entry form.

Before You Begin

Perform the procedure in the [Accessing the Administration Interface for the MeetingPlace Server Agent \(MPSA\) Database](#).

Procedure

1. Perform one of the following actions:
 - ◆ Select **Add Server** to add a Web Server.
 - ◆ Select **Modify Server** to edit an existing Web Server.
2. Enter or edit values. The following table describes the values.

Parameter	Description
Type of web conference server	Controls whether users see Cisco Unified MeetingPlace options or IBM Lotus Sametime online meeting options when configuring the web portion of a meeting. In either case, users can configure a Cisco Unified MeetingPlace meeting. Note: The system does not display the Allow Internet Access field if you select IBM Lotus Sametime.
Number of minutes before a meeting begins for the connect button to appear (Reservationless Only)	The number of minutes that the system displays the Connect button for reservationless meetings.
Hide Meeting Password field	Prevents users from assigning passwords to the meetings that they schedule.
Hide Billing Code field	Prevents users from entering a billing code for the meetings they schedule. Uncheck this field if users need to specify billing codes on a per-meeting basis. Otherwise, Cisco Unified MeetingPlace uses the billing code listed in the profile of the meeting scheduler.
Hide Number of Participants field	Prevents users from specifying the number of callers for the meetings they schedule.
Hide Entry Announcement field	Prevents users from changing the entry announcement options for the meetings they schedule. By default, Cisco Unified MeetingPlace automatically sets up meetings based on the preferences specified in the scheduler profile. Displaying this field in the scheduling form allows the meeting scheduler to change the entry announcement options on a per-meeting basis.
Hide Departure Announcement field	Prevents users from changing the departure announcement options for the meetings they schedule. By default, Cisco Unified MeetingPlace automatically sets up meetings based on the preferences specified in the scheduler profile. Displaying this field on the scheduling form allows the meeting scheduler to change the departure announcement options on a per-meeting basis.

Hide Enable Recording field	Prevents users from recording meetings.
Hide Screened Entry field	Prevents users from using the screened entry option when scheduling meetings.
Hide Publicly Listed Meeting field	Prevents users from determining whether their individual meetings are listed on the Cisco Unified MeetingPlace search page. Instead, this determination is based on the default settings in their user profile.
Hide Allow Internet Access field	Prevents users from determining whether their individual meetings can be accessed from the Internet.
Make Meetings Web Only	<p>Removes the following fields from the Calendar Entry template:</p> <ul style="list-style-type: none"> • Call Me • Phone number • Entry announcement • Departure announcement • Number of locations • Record this meeting <p>This is a system-wide setting. If you have multiple Cisco Unified MeetingPlace systems, all systems will be affected. However, this setting only applies to Cisco Unified MeetingPlace. It does not change the web interface through the click-to-attend link.</p>
Hide Who Can Attend field	Prevents users from choosing the user types who have access to meetings.
Hide Who Can Access MeetingNotes field	Prevents users from choosing the user types who have access to attachments and recordings associated with meetings.
Hide Flex field 1(1)	Prevents users from modifying this field.
Hide Flex field 2 (1)	Prevents users from modifying this field.
Hide Flex field 3 (1)	Prevents users from modifying this field.

Footnote 1: To customize the flex fields, see the Configuration Guide for Cisco Unified MeetingPlace Release 8.0 or the online help in the administrator interface.

3. To customize the subject line that appears in all meeting notifications, enter or edit values in the following fields:

Parameter	Description
MeetingPlace Subject Prefix	Text entered in this field appears in the beginning of the notification subject line. To help users identify that they have been invited to a Cisco Unified MeetingPlace meeting, enter text such as MeetingPlace Meeting or Online Meeting in this field.
MeetingPlace Subject Postfix	Text entered in this field appears at the end of the notification subject line.
MeetingPlace Call Label	Text entered in this field appears before the Cisco Unified MeetingPlace phone number in the notification subject line. Use this parameter to enter a description, such as MeetingPlace Phone Number .

MeetingPlace	Text entered in this field appears before the meeting ID in the notification subject line.
Meeting ID Label	Use this parameter to enter a description, such as Meeting ID .

4. Check **Use Domino Authentication** to enable the IBM Lotus Domino authentication feature. See the [3 How to Configure IBM Lotus Notes for Cisco Unified MeetingPlace for Automatic Authentication](#) for information.

5. Enter or edit values in the following fields to set the scheduling parameters:

Parameter	Description
Max adv days to schedule	Determines how far in the future a user can schedule a meeting. A user cannot schedule a repeating meeting chain that extends past the number of days specified in this field.
# of ports to schedule	Determines the default number of ports that are reserved on the Cisco Unified MeetingPlace system when a meeting is scheduled. A user can change this number on the Calendar Entry form during the scheduling process.
# of video ports to schedule	Determines the default number of video ports that are reserved on the Cisco Unified MeetingPlace system when a meeting is scheduled. A user can change this number on the Calendar Entry form during the scheduling process.

6. Enter a value in the **Remove messages older than** parameter field to periodically clean out the Cisco Unified MeetingPlace mailbox. The system cleans out messages older than the value you enter whenever the Admin CleanUp Agent runs. See the [Enabling the Admin CleanUp Agent](#) for information.

Enabling the Admin CleanUp Agent

Before You Begin

Perform the procedure in the [Accessing the Administration Interface for the MeetingPlace Server Agent \(MPSA\) Database](#).

Procedure

1. Choose **File > Application > Open**.
2. Open the MPSA.nsf database.
3. Navigate to **Shared Code > Agents > Admin CleanUp**.
4. Double-click **Admin CleanUp**.
5. Select **Schedule** in the Runtime area.
6. Change the **Start Running Agent At** parameter to a time you wish to run this agent.
7. Select **OK**.
8. Close the agent.
9. Choose **Yes** to confirm.
10. With the agent name highlighted, select **Enable**.
11. Choose the server on which you want to run this agent.
12. Select **OK**.

8 How to Add Cisco Unified MeetingPlace Features to the IBM Lotus Notes Mail Template

You add Cisco Unified MeetingPlace features to the IBM Lotus Notes client interface by modifying the default IBM Lotus Notes mail template.

- [Modifying the wPreferences Form](#)
- [Adding the MPNewPassword Subform](#)
- [Adding the MPCalendarEntry and MPNotice Subforms](#)
- [Adding the Cisco Unified MeetingPlace Section to the Calendar Entry Form](#)
- [Modifying the Calendar Profile Form](#)
- [Adding New Cisco Unified MeetingPlace Script Libraries](#)
- [Modifying the Notice Form](#)
- [Modifying Existing Script Libraries change title](#)
- [Adding the MeetingPlace Agent to the Mail Template](#)

Modifying the wPreferences Form

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf template.
2. Choose the **wPreferences** form.
3. Locate the Calendar section.
 - It contains three hotspots: FreeTime, Entries, and AutoProcess. Hotspots are URLs that can be programmed.
4. Move the cursor to the end of the hotspot list.
5. Enter **MeetingPlace** as a new hotspot.
6. Double-click the new MeetingPlace hotspot.
7. Choose **Create > HotSpot > Action Hotspot**.
8. Select the lower-right pane.
9. Enter the following formula to program the hotspot:
 1. **REM "DNT";**
 2. **@If(\$PreferencesPage = "MeetingPlace"; @Return(""); "");**
 3. **FIELD \$PreferencesPage := "MeetingPlace";**
 4. **@Command([RefreshHideFormulas])**
10. Save the mailx.ntf template.

Adding the MPNewPassword Subform

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Choose **Shared Code > SubForms** in the mailxx_xMP.ntf template to display the subforms.
3. Select **Edit > Copy**.
4. Highlight the MPNewPassword subform.
5. Switch to mailx.ntf.
6. Select **Edit > Paste** to add the subform in to the corresponding subform list for mailx.ntf.
7. Save the mailx.ntf template.

Adding the MPCalendarEntry and MPNotice Subforms

Before You Begin

Sign in to the IBM Lotus Domino Server as an administrator.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Choose **Shared Code > SubForms** in the mailxx_xMP.ntf template to display the subforms.
3. Choose **Edit > Copy**.
4. Select and copy the **MPCalendarEntry** and **MPNotice** subforms.
5. Switch to mailx.ntf .
6. Choose **Edit > Paste**.
7. Paste the subform into the corresponding subform list for mailx.ntf.
Tip: Press the Ctrl key to select multiple subforms simultaneously.
8. Save the mailx.ntf template.

Adding the Cisco Unified MeetingPlace Section to the Calendar Entry Form

You must modify the calendar entry form so that users who are scheduling meetings can see the Cisco Unified MeetingPlace fields.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Choose the Calendar Entry form in the mailx.ntf template.
3. Scroll to the Scheduler area of the Calendar Entry form.

4. Click in the space above the Scheduler area to create an insertion point.
5. Choose **Create > Resources > Insert Subform**.
6. Choose **MPCalendarEntry**.
7. Select **OK**.
8. Save the mailx.ntf template.

Modifying the Calendar Profile Form

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Choose the Calendar Profile form in the mailxx_xMP.ntf template.
3. Select **MP_ServerNames** and **MP_ServerAddress**. The fields are in the last row of fields at the top of the mailxx_xMP.ntf template.
4. Choose **Edit > Copy**.
5. Switch to the mailx.ntf template.
6. Add a line after the last row of fields at the top of the Calendar Profile form.
7. Choose **Edit > Paste**.
8. Paste the two Cisco Unified MeetingPlace fields in the Calendar Profile form.
9. Select **Calendar & To Do**.
10. Select **MeetingPlace**.
11. Select all text and fields on this tab.
12. Choose **Edit > Copy**.
13. Switch to the mailx.ntf template.
14. Insert a row:
 1. Select **Calendar & To Do**.
 2. Select **To Do**.
 3. Click inside the tab.
 4. Choose **Table > Insert Row**.
15. Create a tab:
 1. Click inside the new row.
 2. Right-click and choose **Table Properties**.
 3. Select **Table Rows**.
 4. Enter **MeetingPlace** in **Tab Label and Caption**.
 5. Close **Properties**.
16. Configure the MeetingPlace tab properties.
 1. Click inside the **MeetingPlace** tab.
 2. Choose **Edit > Paste**.
 3. Select **Yes**.
17. Save the mailx.ntf template.

Adding New Cisco Unified MeetingPlace Script Libraries

Restriction

- Do not modify existing IBM LotusScript code, other than what is described in this document. Only add the Cisco Unified MeetingPlace code sections to existing code in the template.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Select **Script Libraries** in the Shared Code folder of the mailxx_xMP.ntf template to display the list of Script Libraries in the right pane.
3. Locate the following Cisco Unified MeetingPlace script libraries:
 - ◆ MeetingPlace
 - ◆ MeetingPlaceBackGround
 - ◆ MeetingPlaceBackGroundWeb
 - ◆ MeetingPlaceGlobal
 - ◆ MeetingPlaceWeb
4. Press **Shift+Click** to select all the libraries.
5. Right-click the selection.
6. Choose **Copy**.
7. Switch to the mailx.ntf template.
8. Open the Script Libraries list.
9. Right-click in the library list.
10. Choose **Paste**.
11. Save the mailx.ntf template.

Modifying the Notice Form

Add the MeetingPlace section to the Notice form if you want invitations to display Cisco Unified MeetingPlace information.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Copy the MeetingPlace section from the mailxx_xMP.ntf template.
3. Paste the MeetingPlace section in the mailx.ntf template:
 1. Choose the **Notice** form.
 2. Scroll down to the Description section of the form.
 3. Click in the area above the Description line.
 4. Choose **Create > Resources > Insert Subform**.
 5. Choose **MPNotice**.
 6. Select **OK**.
4. Choose **Respond > Delegate** in the Action Pane.
5. (Optional) Choose **View > Action Pane** if the Action Pane is not visible to the right of the form.
6. Right-click the menu choice.
7. Choose **Action Properties**.
8. Select **Action When Hide**.
9. Select **Formula Window**.
10. Scroll to the end of the current formula text in the Edit Formula window.
11. Add a space.
12. Add the following code to the script:
 | **MP_Include="1"**
13. Modify the formulas for the following actions in the same way, adding the same script as in Step 9:
 - ◆ **Respond > Propose New Time**
 - ◆ **Respond with Comments > Delegate**
14. Save the mailx.ntf template.

Modifying Existing Script Libraries change title

You must add Cisco Unified MeetingPlace-specific code to the following functions in the following IBM Lotus Notes mail template script libraries.

Script library	Functions that need to be added to Cisco Unified MeetingPlace code
Common	Options, CSDocSave, CopyProfileValues, CSDocScanForUpdates
CSCalendarEntry	Options, Declaration
CSEventClass	Declarations, Options, RemoveFromMiniView
CSEventNotes	Options, Declarations
CSEventWeb	Options, Declarations
CSUIViewClass	Options, ProcessViewCommand, ViewDragPasteHandler

Restriction

Do not modify existing IBM LotusScript code, other than what is described in this document. Only add the Cisco Unified MeetingPlace code sections to existing code in the template.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Choose **Shared Code > Script Libraries** in the mailxx_xMP.ntf template.
3. Locate the Cisco Unified MeetingPlace-specific code for each library and function listed in the previous table between the "MeetingPlace Begin" and "MeetingPlace End" comment lines.
4. Choose **Edit > Copy**.
5. Select and copy the code (including comment lines, for later identification).
6. Switch to mailx.ntf.
7. Choose **Edit > Paste**.
8. Paste the code in the corresponding script library functions in mailx.ntf.
9. Choose **Other > Database Resources** in the mailxx_xMP.ntf template.
10. Double-click the **Database Script Library**.
11. Choose the **Querydocumentdelete** subquery.
12. Locate the code between the "MeetingPlace Begin" and "MeetingPlace End" comment lines.
13. Choose **Edit > Copy**.
14. Select the code (including comment lines, for later identification).
15. Switch to mailx.ntf.
16. Choose **Edit > Paste**.
17. Paste the code in the corresponding subquery in the Database Script library in mailx.ntf.
18. Save the mailx.ntf template.

Adding the MeetingPlace Agent to the Mail Template

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Designer.

Procedure

1. Open the mailx.ntf and mailxx_xMP.ntf templates.
2. Choose **Form > Shared Code > Agents** in the mailxx_xMP.ntf template.
3. Choose **Edit > Copy**.
4. Select **MPSendInvitations**.
5. Switch to mailx.ntf.
6. Choose **Edit > Paste** to add the agent to the Forms > Shared Code > Agents section of the mailx.ntf template.
7. Save the mailx.ntf template.

9 How to Migrate IBM Lotus Notes Users to Cisco Unified MeetingPlace

You must migrate users to the new Cisco Unified MeetingPlace mail template before they can schedule Cisco Unified MeetingPlace meetings from their IBM Lotus Notes calendar.

- [Migrating a Pilot Group to the Cisco Unified MeetingPlace Mail Template](#)
- [Replacing the Standard Mail Template with the Cisco Unified MeetingPlace Mail Template](#)
- [How to Update the System to Use the New Template](#)

Note: For information about integrating IBM Lotus Notes code in standard IBM Lotus Notes mail templates, see the [8 How to Add Cisco Unified MeetingPlace Features to the IBM Lotus Notes Mail Template](#).

Migrating a Pilot Group to the Cisco Unified MeetingPlace Mail Template

Before you migrate an organization to the new Cisco Unified MeetingPlace mail template, you can deploy the new mail template to a pilot group. If you choose this approach, you must choose the Cisco Unified MeetingPlace mail template for each user individually.

Before You Begin

- Identify the members of the pilot group.
- Sign in as an administrator to the computer of each pilot group member.

Procedure

1. Open the IBM Lotus Notes client.
2. Select **Calendar**.
3. Choose **File > Application > Properties > Design**.
4. Check **Inherit Design from Template**.
5. Do the following:

If the User Is Using	Do This
IBM Lotus Domino Release 6 or 6.5	Replace StdR60Mail with the applicable version of the Cisco Unified MeetingPlace mail template, such as Cisco Unified MeetingPlace Notes Gateway Mail Template Release 6.0.5 or 6.5.5.
IBM Lotus Domino Release 7	Replace StdR70Mail with the applicable version of the Cisco Unified MeetingPlace mail template, such as Cisco Unified MeetingPlace Notes Gateway Mail Template Release 7.0.2.
IBM Lotus Domino Release 8 or 8.5	Replace StdR80Mail with the applicable version of the Cisco Unified MeetingPlace mail template, such as Cisco Unified MeetingPlace Notes Gateway Mail Template Release 8.0 or 8.5.

Replacing the Standard Mail Template with the Cisco Unified MeetingPlace Mail Template

If you choose to deploy Cisco Unified MeetingPlace features to an organization, the easiest method is to delete the standard IBM Lotus Notes mail template and replace it with the Cisco Unified MeetingPlace mail template.

Before You Begin

- Ensure that you have the Cisco Unified MeetingPlace-specific mail template installed on the IBM Lotus Domino Server.
- Sign in to the IBM Lotus Domino Server as an administrator.
- Open an IBM Lotus Domino console session.

Procedure

1. Enter **exit** to shut down the IBM Lotus Domino Server.
2. Delete the mailx.ntf template, where the value of *x* depends on your server version.
 - Note:** Make sure that the mailx.ntf file is deleted; otherwise, IBM Lotus Notes assumes that you have two templates claiming to be the standard IBM Lotus Notes mail template and displays warning messages.
3. Restart the IBM Lotus Domino Server.
4. Change the database properties of the Cisco Unified MeetingPlace-specific mail template after the server restarts:
 1. Choose **File > Application > Properties**.
The system opens the database window.
 2. Select **Design**.
 3. Change the name of the Cisco Unified MeetingPlace mail template:

If You Are Using	Do This
mail60_xMP.ntf	Delete the current template name and enter StdR60Mail , which is the name of the standard IBM Lotus Notes mail template.
mail65_xMP.ntf	Delete the current template name and enter StdR70Mail , which is the name of the standard IBM Lotus Notes mail template.
mail80_xMP.ntf	Delete the current template name and enter StdR80Mail , which is the name of the standard IBM Lotus Notes mail template.
mail85_xMP.ntf	

How to Update the System to Use the New Template

The system automatically starts using the new template the next day. However, you can manually have the system start using the new template at any time if you do not want to wait until the next day.

Caution! Performing this procedure can temporarily affect the performance of the IBM Lotus Domino Server. We recommend that you do this during non-business hours.

- [Manually Updating a Single System to Use the New Template](#)
- [Updating the System to Use the New Template for All Users](#)

Manually Updating a Single System to Use the New Template

Before You Begin

- Sign in as an administrator to the computer where you plan to perform the manual update.
- Open IBM Lotus Notes.

Procedure

1. Select **Mail**.
2. Choose **File > Application > Refresh Design**.

The IBM Lotus Domino Server immediately starts using the new template.

Updating the System to Use the New Template for All Users

Before You Begin

- Sign in to the IBM Lotus Domino Server.
- Open the IBM Lotus Domino console.

Procedure

1. Enter **load design**.
2. Press **Enter**.

The IBM Lotus Domino Server immediately starts using the new template for all users in the system.

Tip: Depending on the number of users, this process might take several minutes.

10 How to Customize Meeting Notifications

End users can receive meeting notifications in IBM Lotus Notes for meetings scheduled from IBM Lotus Notes or from Cisco Unified MeetingPlace.

- [About Using Multiple Notification Programs](#)
- [About Meeting Notification Formats](#)
- [About Notifications for Rescheduled Meetings](#)
- [About Meeting Notification Templates](#)
- [Customizing the Meeting Notification Templates](#)

About Using Multiple Notification Programs

If your organization has both Microsoft Outlook and IBM Lotus Notes, you can install Microsoft Outlook for Cisco Unified MeetingPlace and IBM Lotus Notes for Cisco Unified MeetingPlace on separate servers to support each set of users. Both integrations can point to the same Cisco Unified MeetingPlace system, but must point to different mailboxes.

After you install both integrations, users can schedule Cisco Unified MeetingPlace meetings from IBM Lotus Notes, Microsoft Outlook, or Cisco Unified MeetingPlace.

About Meeting Notification Formats

The format of a meeting notification varies depending on the following:

- The program used to schedule the meeting
- The email program in which the end user receives the notification

The following table describes the format of the meeting notifications that users receive.

Meeting Scheduled From	IBM Lotus Notes Users Receive	Microsoft Outlook Users Receive
Cisco Unified MeetingPlace	IBM Lotus Notes notification (1)	Microsoft Outlook notification (1)
IBM Lotus Notes	IBM Lotus Notes notification (1)	SMTP notification
Microsoft Outlook	SMTP notification	Microsoft Outlook notification (1)

Footnote 1: If a user accepts the meeting, it will be displayed on their calendar.

About Notifications for Rescheduled Meetings

Notifications for rescheduled meetings contain a different set of information than the information in the original meeting notification. The information in the notification for the rescheduled meeting depends on the interface that was used to reschedule the meeting.

You can only reschedule a meeting using the interface from which you originally scheduled the meeting. So if you scheduled a meeting from IBM Lotus Notes, you can only reschedule it from IBM Lotus Notes and if you scheduled a meeting from Cisco Unified MeetingPlace, you can only reschedule it from Cisco Unified MeetingPlace.

- [Notifications for Meetings Rescheduled From IBM Lotus Notes](#)
- [Notifications for Meetings Rescheduled From Cisco Unified MeetingPlace](#)

Notifications for Meetings Rescheduled From IBM Lotus Notes

When you schedule a meeting from IBM Lotus Notes and then reschedule it from IBM Lotus Notes, the system sends a meeting notification for the rescheduled meeting that has the same information as the original notification, including the click-to-attend link. If the user accepts the rescheduled meeting, the system updates their calendar.

Note: IBM Lotus Notes does not allow you to change the meeting ID, meeting password, or the Allow Internet Access option when you reschedule a meeting from IBM Lotus Notes.

Notifications for Meetings Rescheduled From Cisco Unified MeetingPlace

When you schedule a meeting from Cisco Unified MeetingPlace and then reschedule it from Cisco Unified MeetingPlace, the system sends a meeting notification with different subject and body fields than those in the original meeting notification, as noted in the following table:

Meeting Notification for Original Meeting	Meeting Notification for Rescheduled Meeting
Subject: Meeting name, date/time	Subject: Meeting name, meeting ID, meeting password (if required)
Body: Click-to-attend link, meeting information	Body: Click-to-attend link, original meeting information

The system updates the click-to-attend link and allows users to attend the rescheduled meeting.

About Meeting Notification Templates

The following table describes the templates used to generate meeting notifications.

Template Name	Description
mailxx_xxMP.ntf	Generates meeting and reminder notifications for meetings scheduled from IBM Lotus Notes. A template is included for each supported version of IBM Lotus Domino and IBM Lotus Notes (for example, mail65_3.ntf is used for users of IBM Lotus Domino Release 6.5 and IBM Lotus Notes Release 6.5.3).
NotifySchedule.tpl	Generates meeting notifications for IBM Lotus Notes users for meetings that are scheduled from Cisco Unified MeetingPlace.
NotifyReschedule.tpl	Generates updated notices for IBM Lotus Notes users for meetings that are rescheduled from Cisco Unified MeetingPlace.
NotifyCancel.tpl	Generates cancellation notices for IBM Lotus Notes users for meetings that are canceled from Cisco Unified MeetingPlace.

Customizing the Meeting Notification Templates

You can customize the meeting notification templates for meetings that are scheduled from Cisco Unified MeetingPlace. Each template contains tags that contain the text that appears in the meeting notifications. When the system generates a meeting notification, IBM Lotus Notes replaces the tags with the appropriate information from the Cisco Unified MeetingPlace database.

Consider adding tags with the following information to your meeting notifications:

- Instructions about how to attend meetings and access attachments.
- Alternate phone numbers for your Cisco Unified MeetingPlace system, such as a toll free number or internal company extension.
- A list of meeting invitees.
- Information about how to record a meeting.

Before You Begin

Sign in to the IBM Lotus Domino Server as an administrator.

Procedure

1. Access the meeting notification templates by navigating to C:\Cisco\Cisco MeetingPlace for Notes.
2. Using Notepad, open the .tpl meeting notification template that you want to customize.

Caution! Using a word processing program other than Notepad can change the template file extension and produce an unreadable meeting notification. Notepad can automatically save a template without changing its .tpl extension.
3. As applicable, add the tags that are listed in the following table to your Cisco Unified MeetingPlace meeting notification template.

Tag	Description
<!--#LATD AttendMeetingHint -->	How to attend a meeting.
<!--#LATD MeetingNotesHint -->	How to access MeetingNotes.
<!--#LATD C_AltPhoneNumName1 -->	Label for notifications.
<!--#LATD C_AlternatePhoneNum1-->	First alternate phone number.
<!--#LATD C_AltPhoneNumName2 -->	Second label for notifications.
<!--#LATD C_AlternatePhoneNum2 -->	Second alternate phone number.
<!--#LATD C_AltPhoneNumName3 -->	Third label for notifications.
<!--#LATD C_AlternatePhoneNum3 -->	Third alternate phone number.
<!--#LATD ListInvitees -->	List of meeting invitees.
<!--#LATD fRecordConference -->	Whether the meeting is scheduled to be recorded.
<!--#LATD WhoCanListen -->	Who can access the meeting recording (None, anyone, Cisco Unified MeetingPlace users, or invited users).

Note: When you add a tag to a meeting notification template, the system displays the information in the same location in the meeting notification where you entered it. Place more important information at the top of the meeting notification template.

4. To delete a tag from the meeting notification template, delete the applicable tag and label from the template.
5. Save the template as a text file. Make sure that your word processing program does not change the .tpl extension of the file.

11 Troubleshooting IBM Lotus Notes for Cisco Unified MeetingPlace

- [Troubleshooting: What to Do First](#)
- [Resolving Error Messages](#)
- [Troubleshooting Mail Template Settings](#)
- [Resolving Scheduling Errors When the "Allow Internet Access" Option is Checked](#)
- [Resolving Problems when LNNotify Does not Start](#)
- [Resolving Java.io.fileNotFound Exception](#)
- [Resolving Cross Certify Errors](#)
- [Problems with Meeting Attachments](#)
- [Problems With Meeting Notifications](#)
- [Problem Accessing Online Help From the "About This Database" Page](#)

Troubleshooting: What to Do First

If you have scheduling, attendance, or notification problems, perform the following three procedures in the order presented to make sure that IBM Lotus Notes has not lost any of its connections. If you still experience the same problem after completing these procedures, continue with the remaining troubleshooting topics in this section.

- [Verifying That the Windows Services Are Running](#)
- [Verifying That MPNotify and MPAgent Can Sign In](#)
- [Checking the Windows Event Viewer for Errors](#)

Verifying That the Windows Services Are Running

Restriction

Running some services, such as MPAgent, can use as much as 90 percent of your CPU. Fortunately, these services run at a low priority so the CPU spikes do not impact important system functions.

Before You Begin

Sign in as an administrator to the Cisco Unified MeetingPlace Web Server that has the IBM Lotus Notes for Cisco Unified MeetingPlace integration installed on it.

Procedure

1. Choose **Start > Programs > Administrative Tools > Services**.
2. Verify that the following services are running:
 - ◆ Cisco MeetingPlace Gateway SIM
 - ◆ Cisco MeetingPlace Notification Gateway
 - ◆ Cisco Unified MeetingPlace Agent Service
 - ◆ Cisco Unified MeetingPlace Audio Service
 - ◆ Cisco Unified MeetingPlace Connect Application Service
 - ◆ Cisco Unified MeetingPlace Connect Gateway
 - ◆ Cisco Unified MeetingPlace for Notes Gateway

Note: If you cannot start the Cisco Unified MeetingPlace for Notes Gateway service, make sure that the Cisco Unified MeetingPlace account has been set up to use the new Cisco Unified MeetingPlace mail template. See the [6 How to Configure the IBM Lotus Notes Gateway Account to Use the Mail Template](#).

 - ◆ Cisco Unified MeetingPlace for Single Sign On
 - ◆ Cisco Unified MeetingPlace Replication Service
 - ◆ Cisco Unified MeetingPlace Web Server
 - ◆ (Optional) Cisco Unified MeetingPlace Gateway for Cisco WebEx, if this is installed
3. If the services are not running, restart them.

Verifying That MPNotify and MPAgent Can Sign In

Restriction

Running some services, such as MPAgent, can use as much as 90 percent of your CPU. Fortunately, these services run at a low priority so the CPU spikes do not impact important system functions.

Before You Begin

Sign in as an administrator to the Cisco Unified MeetingPlace Web Server that has the IBM Lotus Notes for Cisco Unified MeetingPlace integration installed on it.

Procedure

1. Open the Gateway Configuration utility.
2. Select **Properties**.
3. Select the **Notes Gateway** tab.
4. Check **Verbose Logging**.
5. Select **OK**.
6. Right-click the Gateway Configuration utility and select **Eventlog**.

The system displays the Gateway SIM eventlog.

7. Stop and restart the following services:
 - ◆ Cisco Unified MeetingPlace
 - ◆ Cisco Unified MeetingPlace Notification Gateway
8. View the Gateway SIM eventlog.

The eventlog should display entries that show the MPNotify and MPAgent signing in to the IBM Lotus Domino Server and Cisco Unified MeetingPlace, similar to the following:

```
12/17 12:20:06 MPNotify Information:[2] No new messages to
process
12/17 12:20:07 MPNotify Information:[2] Domino server
CN=ServerName is available
12/17 12:19:08 mpagent Success:Registered for CS events
12/17 12:19:08 mpagent Success:Successfully logged into
MeetingPlace
12/17 12:19:08 MPNotify Information:MeetingPlace login
completed
12/17 12:18:55 mpagent Success:The MPAgent has started
successfully.
12/17 12:18:51 mpagent Information:Service started
12/17 12:18:43 MPNotify Information:Service started
```

9. If the IBM Lotus Notes Gateway service is not signing in to the IBM Lotus Domino Server, check to see if the IBM Lotus Notes client on the Cisco Unified MeetingPlace Web Server that has the IBM Lotus Notes for Cisco Unified MeetingPlace integration installed on it can view its mail database. If the mail database is not accessible, see the IBM Lotus Notes documentation to troubleshoot this problem.
10. If the MPAgent and MPNotify services cannot sign in to the Cisco Unified MeetingPlace system, verify that the Cisco Unified MeetingPlace system is up and running and that you have network connectivity.

Note: After you finish troubleshooting, we recommend that you turn off verbose logging.

Modifications made to verbose logging will only take effect after you stop and restart the service.

Checking the Windows Event Viewer for Errors

You can use the Windows Event Viewer to diagnose directory, user account, and permission errors.

Before You Begin

Sign in as an administrator to the Cisco Unified MeetingPlace Web Server that has the IBM Lotus Notes for Cisco Unified MeetingPlace integration installed on it.

1. Choose **Start > Programs > Administrative Tools > Event Viewer**.
2. Select a log name in the left pane of the Event Viewer window to view events for that log.
3. Look for any directory, user account, and permission errors.
4. Troubleshoot the errors.

Resolving Error Messages

- [Resolving Error Messages Related to Joining Meetings](#)
- [Resolving Error Messages Related to Scheduling Problems](#)
- [Resolving Error Messages Related to Incorrect Profile Information](#)
- [Resolving Error Messages Related to System Setup](#)
- [Resolving Error Messages Related to Errors Validating a User Agent Execution Access](#)
- [Resolving Error Messages Related to Java AccessControl](#)
- [Resolving Error Messages Related to the Connection Between Cisco Unified MeetingPlace and IBM Lotus Domino](#)
- [JavaScript Error Messages When Selecting the URL to Attend the Meeting](#)

Resolving Error Messages Related to Joining Meetings

Error Message: Unable to get a MeetingPlace session ID

Explanation: You may see this error message when you are trying to join a meeting that was scheduled on an external web server. This is due to an incomplete installation of the external server.

Recommended Action: To permit users to use the Cisco Unified MeetingPlace for Notes Gateway on an external web server, make sure that you complete one of the following:

- ◇ Install the MP Notes Gateway on the external web server.
- ◇ Manually copy all 33 Notes-related template files from the internal web server at C:\Program Files\Cisco Systems\MPWeb\Template to the same location on the external web server.

Related Topics

- [2 Installing the IBM Lotus Notes for Cisco Unified MeetingPlace Gateway](#)

Resolving Error Messages Related to Scheduling Problems

Error Message: You are currently unable to schedule Cisco Unified MeetingPlace meetings because you are either offline or working on a local copy of your mail database. Please note that you must be online and your mail database must be located on the IBM Lotus Domino server to allow scheduling of Cisco Unified MeetingPlace meetings.

Explanation: This error occurs when the MPSA.nsf file (the MeetingPlace Server Agent Database) is not visible to IBM Lotus Notes. The client thinks the MeetingPlace Server Agent Database is offline.

Recommended Action: Complete the following procedure.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Administrator.

Procedure

1. Verify that the MPSA.nsf file (the MeetingPlace Server Agent Database) is present on the IBM Lotus Domino Server in the correct location at C:\Lotus\Domino\Data.
If you installed IBM Lotus Notes in a different location, the system might have installed the MPSA.nsf file in the client data directory. If this is the case, copy it to the C:\Lotus\Domino\Data directory.
2. Verify that the MPSA.nsf file (the MeetingPlace Server Agent Database) is signed and that Cisco Unified MeetingPlace has permission to run unrestricted LotusScript/Java agents on your client.

Related Topics

- [Signing the MeetingPlace Server Agent \(MPSA\) Database Template](#)

Resolving Error Messages Related to Incorrect Profile Information

Error Message: Error Message: Unable to access Cisco Unified MeetingPlace resources because your Cisco Unified MeetingPlace profile information is incorrectly entered in the Public Name and Address Book.

Explanation: This error appears when IBM Lotus Domino authentication is being used and the Cisco Unified MeetingPlace user ID of the scheduler was not entered correctly in the IBM Lotus Domino address book.

Recommended Action: Update the IBM Lotus Domino address book with the Cisco Unified MeetingPlace user ID of the scheduler.

Resolving Error Messages Related to System Setup

Error Message: The Administrator has not set up the Cisco Unified MeetingPlace System. Please exit and notify the Administrator.

Explanation: The MeetingPlace Server Agent Database has not yet been created and configured on the IBM Lotus Domino Server.

Recommended Action: Complete the steps in the [Creating the MeetingPlace Server Agent \(MPSA\) Database](#).

Resolving Error Messages Related to Errors Validating a User Agent Execution Access

Error Message: Error validating user's agent execution access [4000] (QuerySave)

Explanation: This error occurs when you sign the MPSA.nsf file (the MeetingPlace Server Agent Database) or Cisco Unified MeetingPlace mail templates (for example, mail60_05MP.ntf, mail65_5MP.ntf, or mail70_2MP.ntf) with the wrong user ID.

Recommended Action: Verify that the MPSA.nsf file (the MeetingPlace Server Agent Database) is signed with the Cisco Unified MeetingPlace ID and that the user, Cisco Unified MeetingPlace, has permission to run unrestricted LotusScript/Java agents on your client. See the [Signing the MeetingPlace Server Agent \(MPSA\) Database Template](#).

Resolving Error Messages Related to Java AccessControl

Error Message: AccessControl Exception java.security.AccessControlException.

Explanation: You have not correctly modified the java.policy file.

Recommended Action: Check the java.policy file to make sure it has the proper syntax. See the [Editing the java.policy File](#).

Resolving Error Messages Related to the Connection Between Cisco Unified MeetingPlace and IBM Lotus Domino

Error Message: A connection cannot be established between Cisco Unified MeetingPlace and IBM Lotus Domino. Contact your IBM Lotus Notes Administrator.

Recommended Action: Complete the following procedure.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Launch IBM Lotus Domino Administrator.

Procedure

1. Verify that the IBM Lotus Domino Server is running.
2. Sign in to the Cisco Unified MeetingPlace Web Server as an administrator.
3. Verify that the Cisco Unified MeetingPlace services are running.
4. Open the MPSA.nsf database from the Domino Administrator.
5. Choose **Administration** from the left pane.
6. Select **Edit/Create Profile Document** at the top of the right pane, to open the Cisco Unified MeetingPlace System Profile Document.
7. Verify that the URLs for Server Address and External Server Address are correct in the Cisco Unified MeetingPlace Server Settings section. If they are not correct, update them as follows:
 1. Choose **Modify Server**.
 2. Update the **MeetingPlace Web CGI URL** and **External MeetingPlace Web CGI URL** fields.

Related Topics

- [Verifying That the Windows Services Are Running](#)
- [Modifying the Cisco Unified MeetingPlace Server Settings](#)

JavaScript Error Messages When Selecting the URL to Attend the Meeting

Problem: The system displays JavaScript errors when selecting the attend URL link.

Explanation: You are using an unsupported web browser.

Solution: For browser support information, see the *System Requirements for Cisco Unified MeetingPlace Release 8.0* : [Cisco Unified MeetingPlace Release 8.0 -- System Requirements for Cisco Unified MeetingPlace Release 8.0](#).

Troubleshooting Mail Template Settings

Problem: Users cannot schedule meetings, or they can schedule meetings but the system does not send a notification.

Explanation: The mail template is not signed.

Solution: Perform the following procedure.

Procedure

1. Verify that the mail template that is being used by the IBM Lotus Notes client is signed. See the [Signing the Cisco Unified MeetingPlace Mail Template](#).
2. Verify that the mail template that is being used by the gateway account is signed.

3. Verify that the user who signed the mail template and the MeetingPlace Server Agent Database (mpsa.nsf) can run unrestricted methods and operations and restricted LotusScript/Java agents.
4. If that user does not have the permissions identified in Step 3, sign the mail template and the MeetingPlace Server Agent (MPSA) database template again. See the [Signing the MeetingPlace Server Agent \(MPSA\) Database Template](#) and the [Signing the Cisco Unified MeetingPlace Mail Template](#).
5. Refresh the design of the end user and gateway account.

Related Topics

[Granting Permission to Run Agents on the IBM Lotus Domino Server](#)

Resolving Scheduling Errors When the "Allow Internet Access" Option is Checked

Problem: There are errors when scheduling a Cisco Unified MeetingPlace meeting when the "Allow Internet Access" option checked.

Explanation: You may have entered a blank value for either the internal or external Web Server URLs when you installed IBM Lotus Notes.

Solution: Open the MPSA.nsf database and add the missing URL. See the [Adding a Cisco Unified MeetingPlace Profile to the MeetingPlace Server Agent \(MPSA\) Database](#) for information.

Resolving Problems when LNNotify Does not Start

Problem: LNNotify does not start. On startup, the system displayed an error message that there is either an internal Windows error or an internal service error.

Explanation: The Cisco Unified MeetingPlace gateway account does not have a Cisco Unified MeetingPlace mail template associated with it.

Solution: Verify that the mail template is appropriate for the IBM Lotus Notes mail template that you are using (for example, mail60_05MP.ntf, mail65_5MP.ntf, mail70_2MP.ntf). Follow the procedure in the [Modifying the Cisco Unified MeetingPlace Server Settings](#).

Resolving Java.io.fileNotFound Exception

Problem: The Java.io.FileNotFoundException exception occurs when a meeting is scheduled on the IBM Lotus Domino console.

Explanation: This error occurs when you have set up your system to receive, but not to send, HTTPS requests.

Solution: Verify that you are using SSL by completing the following procedure.

Before You Begin

- Sign in to the IBM Lotus Domino Server as an administrator.
- Open IBM Lotus Domino Administrator.

Procedure

1. Open the MPSA.nsf database.
2. Choose **Administration**.
3. From the Administration page, choose **Edit/Create Profile Document**.
4. Select **Modify Server**.
5. Verify that the **Use SSL** check box is checked.

Related Topics

[Adding a Cisco Unified MeetingPlace Profile to the MeetingPlace Server Agent \(MPSA\) Database](#)

Resolving Cross Certify Errors

Problem: The system displays the Cross Certify window when trying to open the IBM Lotus Notes calendar.

Explanation: The system displays the Cross Certify window if the database template was not signed after installing IBM Lotus Notes.

Solution: Complete the procedure in the [Signing the MeetingPlace Server Agent \(MPSA\) Database Template](#).

Problems with Meeting Attachments

Problem: Invited users do not receive attachments for meetings that are scheduled through Cisco Unified MeetingPlace.

Explanation: The profile of the meeting scheduler is not set up to send out attachments.

Solution: Complete the following procedure.

Before You Begin

Sign in to the Cisco Unified MeetingPlace Administration Center as an administrator.

Procedure

1. Select **User Configuration > User Profiles**.
2. Locate the user profile by doing the following:
 1. Select a search rule.
 2. Enter the first one or two characters of the user or meeting scheduler name.
 3. Select **Search**.
3. Select the user from the search results list.
4. Select **Edit**.
5. Ensure that the Send attachments field is set to **Yes**.
6. Select **Save**.

Problems With Meeting Notifications

Problem: When scheduling a Cisco Unified MeetingPlace meeting through IBM Lotus Notes, invited users do not receive meeting notifications.

Explanation: The User Name field in the IBM Lotus Domino account of the invited user does not match the email address field in the Cisco Unified MeetingPlace profile for that user.

Solution: Update the email address of the Cisco Unified MeetingPlace profile for the invited user to match the User Name field in the IBM Lotus Domino account.

Problem: When scheduling a meeting through Cisco Unified MeetingPlace, invited users do not receive meeting notifications.

Explanation: This problem occurs when the IBM Lotus Notes gateway account mailbox is full, or there is no more space on the system hard drive.

Solution: Check the mailbox and hard drive space of the IBM Lotus Domino Server where the templates and gateway account mailbox are installed. If the mailbox or hard drive is full, delete or archive unwanted emails or files to create more space.

Problem: When scheduling a meeting through Cisco Unified MeetingPlace, invited users do not receive meeting notifications.

Explanation: This problem occurs when:

- ◇ The profile of the invited user is not set up to receive meeting notifications.
- ◇ The profile of the meeting scheduler is not set up to send meeting notifications.

Solution: Complete the following procedure to verify whether user profiles are set up to send and receive meeting notifications.

Before You Begin

Sign in to the Cisco Unified MeetingPlace Administration Center as an administrator.

Procedure

1. Select **User Configuration > User Profiles**.
2. Locate the user profile by doing the following:
 1. Select a search rule.
 2. Enter the first one or two characters of the user or meeting scheduler name.
 3. Select **Search**.
3. Select the user from the search results list.
4. Select **Edit**.
5. Ensure that the E-mail type field is set to **LotusNotes**.
6. Ensure that the Can send notifications field is set to **Yes**.
7. Ensure that the Can receive notifications field is set to **Yes**.
8. Select **Save**.

Problem: IBM Lotus Notes users do not receive meeting notifications. This happens after the users have received meeting notifications previously and can occur when scheduling a meeting through Cisco Unified MeetingPlace Conference Manager or Cisco Unified MeetingPlace Web Server.

Explanation: Back-end notifications begin to fail if the IBM Lotus Notes account for Cisco Unified MeetingPlace exceeds 5000 documents. This is caused by a default limitation on the IBM Lotus Domino Server where it is unable to handle index files larger than 5000 documents.

See the following example in the IBM Lotus Domino Server console:

```
index of [some_number_greater_than_5000] documents exceeds limit
(5000), aborting: Maximum allowable documents exceeded for a
temporary full text index.
```

Example:

```
12/03/2009 12:14:46 PM Opened session for Meeting
Place/[your_domain] (Release 8.0.1).
12/03/2009 12:14:53 PM Full text operations on database
'mail\meetingplace.nsf' which is not full text indexed. This is
extremely inefficient.
12/03/2009 12:14:53 PM Full Text message: index of 6001 documents
exceeds limit (5000), aborting: Maximum allowable documents
exceeded for a temporary full text index.
```

Recommended Action: Perform the following procedure to verify that meeting notifications can be received by IBM Lotus Notes users.

Procedure

1. Navigate to the IBM Lotus Domino Server installation folder.
2. Open the file called notes.ini.

3. At the end of the file, add these two lines:
 - ◆ Temp_Index_Max_Doc=10000
 - ◆ FT_Max_Search_Results=10000
4. Restart the IBM Lotus Domino Server.

Problem Accessing Online Help From the "About This Database" Page

Problem: The online help for IBM Lotus Notes cannot be accessed by selecting the help link on the About This Database page.

Solution: Press the F1 key while the cursor is present in any of the Cisco Unified MeetingPlace-specific fields in the Calendar Entry form to access the online help.

12 About Upgrading to Cisco Unified MeetingPlace for IBM Lotus Notes Release 8.0 from Release 7.0

Restrictions

- Cisco Unified MeetingPlace does not support mixed template environments. If you are upgrading from one release of IBM Lotus Domino to another, you must upgrade all users to the same server and template environment.

Before You Begin

- Verify that you are currently using supported releases of the IBM Lotus Domino Server and IBM Lotus Notes clients. For system requirements, see the *System Requirements for Cisco Unified MeetingPlace Release 8.0* at:
http://docwiki.cisco.com/wiki/Cisco_Unified_MeetingPlace_Release_8.0_--_System_Requirements_for_Cisco_U

Procedure

- To upgrade to IBM Lotus Notes for Cisco Unified MeetingPlace Release 8.0, simply follow the instructions in this guide.